



# R:Twain2PDF 11

Manual

by R:BASE Technologies, Inc.

Welcome to R:Twain2PDF 11!

The R:BASE TWAIN to PDF Output Utility!

3

# **Table of Contents**

Part I	Introduction	5
1	Introducing R:Twain2PDF 11	
	Copyrights	
	License	
	Complimentary Support	
Part II	Installation	12
1	System Requirements	
2	Things You Will Need	
3	Software Installation	
4	Plugin Activation	
_	R:BASE	
	R:Compiler for R:BASE	
	Runtime for R:BASE	
Part III	Uninstall	18
Part IV	Using R:Twain2PDF	20
1	User Interface	
	Tool Bar	
	Add/Delete Images	
	Select Source	
	Image Compression PDF Document Properties	
	General	
	Security	
	View	
	R:Twain2PDF Image Editor	
	Menu Bar	
	Command Syntax	
3	Examples	
	Example 1 Example 2	
	Example 3	
	Example 4	
Part V	Technical Support	32
Part VI	Useful Resources	34
Part VII	Feedback	36

#### Index

38



#### 1 Introduction

#### 1.1 Introducing R:Twain2PDF 11

R:Twain2PDF is a compact utility program placed into a easy-to-use interface for gathering JPG images and TWAIN sources to produce PDF documents, with full ADF (automatic document feeder) support. You can select from a list of available TWAIN sources or from a scanner to capture images. R:Twain2PDF uses the TWAIN driver which is included with your scanner or TWAIN device, and not the actual product software. Image compression options for R:Twain2PDF include Flate and Jpeg.

The PDF Document Properties allow you to add document information to the output. R:Twain2PDF supports encryption level option for 40 bit, 128 bit, 128 bit AES, and 256 bit AES. Permissions may be assigned for users to print, modify the document structure, copy information from the document, and modify annotations. Several Page Layout, Page Mode, and Viewer Preferences are available.

R:Twain2PDF can be launched with the available executable, or can be launched behind the scenes within an application using the available Plugin, both of which that are provided with the software.

Being fully compatible with R:BASE, R:Twain2PDF includes a Plugin for automation of scanning documents within your R:BASE applications. Or, you can use the graphic user interface to quickly create secure PDF documents.

#### 1.2 Copyrights

Information in this document, including URL and other Internet web site references, is subject to change without notice. The example companies, individuals, products, organizations and events depicted herein are completely fictitious. Any similarity to a company, individual, product, organization or event is completely unintentional. R:BASE Technologies, Inc. shall not be liable for errors contained herein or for incidental consequential damages in connection with the furnishing, performance, or use of this material. This document contains proprietary information, which is protected by copyright. Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written consent of R:BASE Technologies, Inc. We reserve the right to make changes from time to time in the contents hereof without obligation to notify any person of such revision or changes. We also reserve the right to change the specification without notice and may therefore not coincide with the contents of this document. The manufacturer assumes no responsibilities with regard to the performance or use of third party products.

Products that are referred to in this document may be either trademarks and/or registered trademarks of the respective owners. The publisher and the author make no claim to these trademarks.

The software described in this document is furnished under a license agreement. The software may be used or copied only in accordance with the terms of that agreement. Any unauthorized use or duplication of the software is forbidden.

R:BASE Technologies, Inc. may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. Except as expressly provided in any written license agreement from R:BASE Technologies, Inc., the furnishing of this document does not give you any license to these patents, trademarks, copyrights, or other intellectual property.

#### Trademarks

R:BASE®, Oterro®, RBAdmin®, R:Scope®, R:Mail®, R:Charts®, R:Spell Checker®, R:Docs®, R:BASE Editor®, R:BASE Plugin Power Pack®, R:Style®, RBZip®, R:Mail Editor®, R:BASE Dependency Viewer®, R:Archive®, R:Chat®, R:PDF Form Filler®, R:FTPClient®, R:SFTPClient®, R:PDFWorks®, R:Magellan®, R:WEB Reports®, R:WEB Gateway®, R:PDFMerge®, R:PDFSearch®, R:Documenter®, RBInstaller®, RBUpdater®, R:AmazonS3®, R:GAP®, R:Mail Viewer®, R:Capture®, R:Synchronizer®, R:Biometric®, R:CAD Viewer®, R:DXF®, R:Twain2PDF®, R:Scheduler®, R:Scribbler®, R:SmartSig®, R:OutLink®, R:HASH®, R:JobTrack®, R:TimeTrack®, R:Manufacturing®, R:QBDataDirect®, R:QBSynchronizer®, and R:QBDBExtractor®, and Pocket R:BASE® are trademarks or registered trademarks of R:BASE

Copyright © 1982-2025 R:BASE Technologies, Inc.

Technologies, Inc. All Rights Reserved. All other brand, product names, company names and logos are trademarks or registered trademarks of their respective companies.

Windows, Windows 11-10, Windows Server 2025-2016, Azure Maps, Word, Excel, Access, SQL Server, and Outlook are registered trademarks of Microsoft Corporation. OpenOffice is a registered trademark of the Apache Software Foundation.

Printed: July 2025 in Murrysville, PA

First Edition

#### 1.3 License

#### **R:BASE TECHNOLOGIES, INC. LICENSE AGREEMENT**

#### R:Twain2PDF 11 Single Seat License

This is a legal agreement between you, the end user ("**Licensee**"), and R:BASE Technologies, Inc. ("**RBTI**"). Please read the terms and conditions of this License Agreement before using this software. By you selecting "I accept the license agreement" and clicking "Next" during product installation means you expressly accept the terms and conditions of this Agreement. If you do not accept the terms and conditions of this Agreement. If you do not accept the terms and conditions of this Agreement. If you do not accept the terms and conditions of this Agreement. If you do not accept the terms and conditions of this Agreement. If you do not accept the terms and conditions of this Agreement, you must stop installing the Product and click "Cancel". Your money will be refunded based upon proof of purchase, and in compliance with the return period described in the LIMITED WARRANTY below. A violation of the License, brings damage both financially and to the reputation of RBTI, and in the occurrence of either, both termination of the license agreement and civil damages will be vigorously sought. Once you have clicked "I accept the license agreement", you are entitled to use the Product under the following terms and conditions of this Agreement:

#### LICENSE

This RBTI License Agreement permits you to use one copy of the R:Twain2PDF computer software with associated utilities (the "**Program**") and accompanying user documentation (the "**Documentation**") on any single computer. If you do not have a Site License or at least one 5 Seat Add-On License, this program can only be installed on a single machine. However, you can open multiple sessions and be connected to the same and/or other local or network databases on the same machine simultaneously. (The 5 Seat Add-On License permits additional seats to access the Program, in 5 seat increments if each is physically linked to a single file server and you have obtained a separate license for a Single Seat version of the Program. 5 Seat Add-On Licenses must be licensed at the same Single Seat version). A Program is "being used" on a computer when it is loaded into a temporary memory or installed on a hard drive in the computer. However, a copy of the Program installed on a network server for the sole purpose of distribution to other computers is not "being used". Each seat having access to the Program must have an appropriate license. If you anticipate that the number of seats with access to the Program will exceed the number of seats for which you are licensed, you must take steps to ensure that the appropriate licenses are obtained for each seat.

#### **5 SEAT ADD-ON AND SITE LICENSES**

If a printed or other form of "hard-copy" License accompanied the copy of the Program you received whose terms vary from this agreement, then the hard-copy License governs your use of the Program. 5 Seat Add-On and Site Licenses allow you to install the Program on the total number of machines for which you are licensed only.

#### SATELLITE LICENSES

A Satellite License permits a Licensee to use one copy of the copy of the Program on any additional single computer, for additional development to accompany an existing Single Seat License. The Satellite License must be licensed to the same user as the existing Single Seat License. Each seat having access to the Program must have an appropriate license.

#### **COPYRIGHT AND RESTRICTIONS**

RBTI retains full ownership rights in the Program and Documentation. You may make a single copy of the Program; to be used solely for backup or archival purposes, or you may transfer the Program onto a single hard disk provided you keep the original solely for backup or archival purposes. Such copies shall be owned by RBTI. You may not copy any printed material or Documentation without prior permission.

You may not decompile, disassemble cross-compile, reverse engineer, or make or distribute any other form of, or derivative work from, the Program. You may not obscure, alter or remove any RBTI copyright, trademark or proprietary rights notices.

#### TRANSFER OF LICENSE

You may not lend, rent or lease the Program or Documentation or any copies to any person. A transfer of license is only authorized through completion of the Consent to Assignment and Assumption of Contract agreement from RBTI. Upon license transfer, you are permanently giving such person possession of all copies of the Program and Documentation, are permanently giving up your right to use the Program and Documentation, and the recipient agrees to the terms of this License Agreement.

#### **STEP UPS AND UPGRADE PURCHASES**

As the Licensee, you are authorized to use the Program only if you are an authorized user of a qualifying product as determined by RBTI. The new license agreement takes the place of the agreement of the qualifying software you stepped up or upgraded from. After you upgrade, you may no longer use the software from which you upgraded. When you install the upgrade, you must uninstall the copy of the qualifying product.

#### **TERM OF LICENSE**

The licensing provided in this License Agreement is perpetual unless you violate any of its terms or conditions, at which time the license will automatically terminate. Upon termination you must return all copies of the Program and Documentation to RBTI or certify in writing to RBTI that all such copies have been destroyed and uninstalled from each workstation and/or network server. RBTI reserves the right to, at its expense and without prior notice, conduct periodic inspections for licensing compliancy. If licensee is found to be in violation of current agreement, RBTI may commence a civil action seeking fines, damages, attorney's fees and injunctive relief and may also, in appropriate circumstances, seek criminal prosecution.

#### **ACTIVATION CODES**

The Program requires activation using a unique code. If you purchase a Single Seat License with or without 5 Seat Add-On Licenses, you agree to comply with the license activation and verification procedure described in this section of the Agreement. The activation technology may prevent your use of the Program if you do not follow the activation process described in this Agreement.

Each activation code is tied to one Windows operating system computer. A dual-boot computer with multiple operating systems cannot activate a Single Seat License on more than one operating system. Any software utilities which alter how the Program is installed on a local drive are not supported. This includes any utilities which alter, remove or transfer the location of the Program on the hard drive, or any hard drive utilities which alter the physical properties of the local drive.

The Program activation can be completed automatically through an Internet connection or manually through a provided email option. In doing so, the Program Registration Number and Computer ID must be provided. License validation allows a number of activations based upon the number of licenses purchased.

If a computer is no longer using the Program, through license transfer or hardware failure, the Activation Key that was used on the computer must be submitted to R:BASE Technologies so the key may be disabled, which will then free up that used activation. Once a key is reported as no longer in use and deactivated, it can no longer be used on that computer. Product deactivation can be performed automatically from within R:BASE. To review the License Key and Activation Key product information, select "Help" > "Product Activation" from the Menu Bar.

Licenses for the Corporate VIP Licenses of the Program are not controlled by activation codes and can be operated from computers that are not connected to the Internet.

#### SOFTWARE SUPPORT

The availability of software support services is subject to the End of Support (EOS) and End of Life (EOL) product life cycle, and to an active Software Assurance Plan. Where applicable, licensees will be provided with an option to upgrade to the current supported version of a software product.

#### LIMITED WARRANTY

RBTI warrants to you, as the initial user, the Program will perform substantially in accordance with the Documentation, provided it is used in unaltered form with functioning equipment and operating systems

for which it was designed. RBTI will, at its option, with proof of payment within 30 days of the invoice date and after the Program with Documentation has been deactivated and uninstalled, and software installer, whether provided by download or other means, permanently deleted from all drives and folders, issue a full refund. These are your sole remedies for any breach of warranty. No exceptions will be made.

#### SERVICES PROVIDED WITH PURCHASE

#### **1. 30-Day Limited Complimentary Technical Support**

#### LICENSEE RESPONSIBILITIES

- To help us expedite the process and provide high quality assistance, the licensee must provide proof of purchase when calling. Proof of purchase is defined as the following: registration number, purchase date, version and build number, and company or individual to which product is registered.
- To have operating system, workstations, and local network installed and functional. RBTI will NOT be responsible for resolving issues not pertaining to the Program.
- Our support staff deals with advanced issues, therefore the person contacting RBTI for assistance should be the system administrator or have other R:BASE/SQL experience and be able to understand and implement the advice given.
- To have the database(s) being converted, safely backed-up before attempting conversion process. RBTI will NOT be held responsible for lost data or corruption as a result of advice given.

#### **R:BASE TECHNOLOGIES, INC. RESPONSIBILITIES**

- To provide quality assistance in a timely manner to aid Licensee in the installation of the product within 30 days of the date of purchase.
- To provide a reasonable solution for any resolvable issue. Not all issues are resolvable, and therefore we will acknowledge the existence of known issues or "bugs" which we are presently aware of, that have no reasonable work-around.

RBTI reserves the right to limit the amount of support time allotted to a maximum of <u>2 HOURS</u> during the 30-Day Complimentary Technical Support Period. We also reserve the right to limit the quantity of calls from a particular Licensee to <u>30 MINUTES</u> in a single day. Issues are dealt with on a case-by-case basis, and are handled at the discretion of the support agent assigned to the case. Complimentary Support is limited to INSTALLATION and ELEMENTARY CONVERSION related issues ONLY. Our support hours are from 10am. to 6pm. Eastern Time.

For assistance on your APPLICATIONS, DESIGN, or ADVANCED CONVERSION issues, we offer Technical Support Plans of various types to meet your needs. Please visit the SUPPORT area of our website at www.rbase.com for details and pricing.

#### 2. Fixes for Known Issues

RBTI will provide continued product fixes for known issues or "bugs" for <u>1 YEAR</u> from the software purchase date. After 1 year, users are urged to acquire the necessary Software Assurance Plan to continue with product support and ongoing activations for reinstallations and license transfers.

#### 3. Enhancement Requests

RBTI will provide continued product enhancements for requested features for <u>1 YEAR</u> from the software purchase date. After 1 year, users are urged to acquire the necessary Software Assurance Plan to continue with product support and ongoing activations for reinstallations and license transfers.

#### 4. Periodic Activations

RBTI will provide periodic product activations of license transfers and/or reinstallations for <u>1 YEAR</u> from the R:BASE purchase date. Any activation requests that occur beyond the 1 Year purchase date will require an active Software Assurance Plan.

#### NO OTHER WARRANTIES

Except as explicitly stated above, RBTI makes no express or implied warranties (including any warranties of merchantability or fitness) with respect to the character, function, or capabilities of the program, the documentation or their appropriateness for any user's purposes. RBTI cannot customize product(s) to meet specific needs in all cases. Examples of customization include, but are not limited to: special

character sets, foreign language adaptations, specific device drivers or other localization issues. Under no circumstances will RBTI be held responsible for product functionality once alterations have been made to accommodate individual needs.

#### **DISCLAIMER OF WARRANTY**

The Program and the accompanying files are sold "as is" and without warranties as to performance or merchantability or any other warranties whether expressed or implied. Because of the various hardware and software environments into which the Program may be put, No warranty of fitness for a particular purpose is offered. Good data processing procedure dictates that any program be thoroughly tested with non-critical data before relying on it. The user must assume the entire risk of using the Program. Any liability of the seller will be limited exclusively to product replacement or refund of purchase price.

#### **HIGH RISK ACTIVITIES**

The Program is not fault-tolerant and is not designed, manufactured or intended for use or resale as online control equipment in hazardous environments requiring fail-safe performance, such as in the operation of nuclear facilities, air traffic control, aircraft navigation or communication systems, direct life support machines, or weapons systems, in which the failure of the Program could lead directly to death, personal injury, or severe physical or environmental damage ("High Risk Activities"). RBTI specifically disclaims any expression or implied warranty of fitness for High Risk Activities.

#### LIMITATIONS ON LIABILITIES

RBTI will not be responsible for any costs or damages associated with loss of the use of the Program or any other resources, loss of business or profits, any loss of data, any third-party claims or costs of substitute programs. In no event will RBTI be liable for any incidental, indirect, special, consequential or punitive damages suffered by the user or any other person or entity, whether from the use of the program or documentation, any failure thereof, or otherwise, even if RBTI or its dealers or agents are aware of the possibility of such damages. In no event will RBTI aggregate liability to you or anyone else exceed two times the license fee you paid for the program and documentation in this package. Because some states do not allow the limitation or exclusion of implied warranties and liabilities for consequential or incidental damages, the above limitations may not apply to you.

#### GENERAL

This License Agreement constitutes the full and complete agreement between parties. RBTI retains all rights not specifically granted herein. RBTI shall not be deemed to have waived any of its rights hereunder or under all copyright laws, trade secrecy laws or otherwise. This Agreement is intended as a legally binding agreement which will be enforced to the full extent permitted under applicable law, in whole or in part. If any one provision of this Agreement is declared invalid or unenforceable, all remaining provisions shall never less remain in effect. The laws of the state of Pennsylvania shall govern this Agreement. RBTI reserves the right to amend, alter, or revoke this agreement at any time. All revisions to this license agreement are available for inspection upon request, supersede conditions in all past agreements, and render prior license agreements void and unenforceable. Both parties named in this license will only be bound to the terms of the most current revision of this agreement.

#### **U.S. GOVERNMENT RESTRICTED RIGHTS**

Use, duplication or disclosure by the Government, its agents or employees is subject to all restrictions imposed by law, regulation or government directive, including but not limited to those restrictions set forth in DFARS 252.227-7013 and 48CFR 52.227-19, as applicable.

R:BASE Technologies, Inc. https://www.rbase.com rbaseinfo@rbase.com

Copyright 1982-2025 R:BASE Technologies, Inc. All Rights Reserved Revised Monday, July 07, 2025

#### **1.4 Complimentary Support**

#### **30 DAY LIMITED COMPLIMENTARY TECHNICAL SUPPORT**

#### A. LICENSEE RESPONSIBILITIES.


- 1. To help us expedite the process and provide high quality assistance, the licensee must provide proof of purchase. Proof of purchase is defined as the following: registration number, purchase date, version and build number, and company or individual to which product is registered.
- 2. To have operating system, workstations, and local network installed and functional. R:BASE Technologies will NOT be responsible for resolving issues not pertaining to the software product.
- 3. Our support staff deals with advanced issues, therefore the person contacting R:BASE Technologies for assistance should be the system administrator or have other R:BASE/SQL experience and be able to understand and implement the advice given.
- 4. To have the database, application, and command files being reviewed, safely backed-up before attempting assistance. R:BASE Technologies will NOT be held responsible for lost data or corruption as a result of advice given.

#### **B. R:BASE TECHNOLOGIES, INC. RESPONSIBILITIES.**

- 1. To provide quality assistance in a timely manner to aid in the installation of the product and elementary conversion of database, application, and command files within 30 days of the date of purchase.
- 2. To provide a reasonable solution for any solvable issue. Not all issues may be solved, and therefore we will acknowledge the existence of known issues, or bugs, which we are presently aware of, that have no reasonable work-around.

R:BASE Technologies reserves the right to limit the amount of support time allotted to a maximum of 2 HOURS during the 30-Day Complimentary Technical Support period. We also reserve the right to limit the quantity of calls from a particular licensee to 30 MINUTES in a single day. Issues are dealt with on a case-by-case basis, and are handled at the discretion of the support agent assigned to the case. Complimentary Support is limited to INSTALLATION and ELEMENTARY CONVERSION related issues ONLY. Our support hours are Monday through Friday, from 10:00 AM to 6:00 PM (EST).

For application, design, or advanced conversion assistance, R:BASE Technologies offers Technical Support Plans of various types to meet your needs. Please visit the Support page at <a href="https://www.rbase.com/support">https://www.rbase.com/support</a> for details and pricing.



#### 2 Installation

#### 2.1 System Requirements

The following system specifications are recommended for the optimal use of R:BASE and R:BASE-related software.

#### Workstation Hardware

- 2-Core 2GHz+ CPU
- 2 GB of available RAM (4 GB recommended)
- 2 GB of available hard disk space
- 1024x768 or higher resolution video adapter and display
- Standard mouse or compatible pointing device
- Standard keyboard

#### Server Hardware

- 2-Core 2GHz+ CPU
- 6 GB of available RAM (8 GB recommended)

#### **Operating System**

- Microsoft Windows 11 (Professional)
- Microsoft Windows 10 (Professional)
- Microsoft Windows Server 2025
- Microsoft Windows Server 2022
- Microsoft Windows Server 2019
- Microsoft Windows Server 2016

#### Network

- Ethernet infrastructure (Gigabyte recommended)
- Internet connection recommended, but not required, for license activation, software updates, and support
- Anti-virus programs should exclude the R:BASE program, and any add-on product, executable and database files

#### 2.2 Things You Will Need

License Key

Before launching the installer, it is recommended that you have your 32-character License Key readily available. The License Key is provided in a document, with the email message, when the software was originally purchased. If you have lost or misplaced your License Key, please contact our Support Staff by email at <a href="mailto:support@rbase.com">support@rbase.com</a>.

• Internet Access

The computer where the software will be launched should have access to the Internet for activation. The Internet access is used to visit the R:BASE Technologies Web site to provide your required Activation Key.

In instances where the software will be installed on a computer that is not connected to the Internet, you must then contact R:BASE Technologies to provide information displayed on the computer screen. Please contact our Product Activation Staff by email at <u>activationkey@rbase.com</u>. The Registration Number must be provided. The Registration Number is displayed on the invoice/order slip, and within the email, when the software was originally purchased.

#### 2.3 Software Installation

The installation of R:Twain2PDF is fully automated and does not require user intervention for the initial setup.

Run the installer ".exe", provided by download, while physically sitting at the workstation to begin the installation process, and read the installer screens for licensing and other information as the program installs.

#### **Installation Directory**

C:\RBTI\RTwain2PDF11

#### **Files Installed**

RTwain2PDF11.exe RTwain2PDF11.rbm RTwain2PDF11.pdf RTwain2PDF11.chm ReadMe.txt License.rtf

#### **Requirements:**

#### Plugin

The R:Twain2PDF 11 Plugin file (RTwain2PDF11.rbm) must be placed in the R:BASE 11 program directory (default: C:\RBTI\RBG11) or the runtime/compiled application directory.

#### 2.4 Plugin Activation

R:BASE Plugins can be used to enhance, or extend R:BASE operations. Current R:BASE Plugins use the .RBM file extension.

To begin using any plugin product, the plugin must be registered for use.

The license type for R:BASE and R:BASE plugin products must match. The license keys supplied with Single Seat and 5 Seat plugin products will only be accepted within Single Seat and 5 Seat versions of R:BASE, and are not accepted within R:Compiler for R:BASE or Runtime for R:BASE programs. The same license structure is also in place for Runtime License Keys for plugin products, where the key will not be accepted within Single Seat and 5 Seat Licenses R:BASE.

#### 2.4.1 R:BASE

To begin using a plugin product, you must register the software within R:BASE by selecting "Help" > "Product Activation" from the main Menu Bar. In this window, select the "Add New" button where you can enter or copy and paste the License Key you received with your product.

Only "Per Seat" License Keys are valid for this entry screen. All "Runtime" License Keys must be registered within R:Compiler for R:BASE or within Runtime for R:BASE separately.

License Informa	tion					×
Enter License	Key:					
Paste			<b>~</b> 0	к	× Cancel	

After entering the License Key, you will see a dialog to prompt for your activation method. The software can be activated automatically over the Internet, or manually by retrieving an Activation Key from R:BASE Technologies by email or over the phone. If you select "Later", you will be reminded each time R:BASE starts to activate your copy.

R:BASE Activation Wizard	9		×
Select activation met	hod:		
	d quickest wa connection is	y to activate your s s established. The v	
	the automatic	activation failed fo il to obtain an Act	
<ul> <li>Activate later</li> </ul>			
	< <u>B</u> ack	<u>N</u> ext >	Cancel

When activating the software manually, you select the e-mail link to launch your email client and send a pre-formatted message to R:BASE Technologies that will contain your License Key and the displayed Computer ID. You will need to provide your R:BASE Registration Number and Computer ID.

R:BASE Activation Wiz	zard		3
To obtain your Act provide the follow			ail link below to e to <mark>this compute</mark> r.
Con	nputer II	D: 944C4	593
E-mail: activationk	ey@rbase.com		
Activation Key:			Paste
	< Back	Next >	Cancel

At any time, you can review your product information by starting R:BASE, and from the Menu Bar clicking on "Help" > "Product Activation". Your R:BASE Registration Number is displayed on the window. You can also enter additional License Keys for R:BASE add-on products.

Product Name	Registration Number	Number of Seats	
R:BASE 11	1100007	5	
R:BASE Plugin Power Pack 11	1100007	5	
R:PDF Works 11	1100007	5	
R:Spell Checker 11	1100007	5	

Please be advised that if you are activating multiple workstations, it is highly recommended that you keep records of the computer name, Computer ID and Activation Key for future reference. Access to this information will prove convenient in the event of a hardware failure or license transfer when uninstalling R:BASE.

Please see: Uninstall/Reinstall

#### 2.4.2 R:Compiler for R:BASE

#### **Runtime License Key**

Runtime license keys for an R:BASE Plugin must be stored within the compiled executable. A specific Runtime License Key would be provided after your purchase of the Runtime software product. Adding a Runtime License to your project can be done by selecting the "Add License" button, and pasting the appropriate Runtime License Key into the displayed dialog window.

Add New License	×
Enter the License Key for your registere	ed product:
Paste	OK Cancel

After a Runtime License is added as a resource, it will be assigned a "Resource ID". This ID consists of the word "License" and an incrementing value for the number of licenses added to the executable.

Plugin File (.RBM)

R:BASE Plugin files can be added and stored within the compiled executable or included within the R:BASE application directory. The Runtime license key pertaining to the R:BASE Plugin must be stored in the compiled executable.


Adding a Plugin to the list of resources can be performed by selecting the "Add Plugin" button on the Tool Bar. You will be prompted to locate the appropriate Plugin file with the .RBM file extension. After a Plugin file is added as a resource, it will be assigned a "Resource ID". This ID consists of the Plugin file name.

#### 2.4.3 Runtime for R:BASE

After R:BASE Plugins are acquired for Runtime for R:BASE applications, the Plugin file must be included in the Runtime application folder, to be loaded when the Runtime application launches.

To load the Plugin, the License Key must be included into the Runtime for R:BASE session by adding the following PROPERTY command within the application startup file:

PROPERTY ADD\_LICENSE ####-####-####+=####-####-####-##### ' '



#### 3 Uninstall

If a computer is no longer using R:Twain2PDF, through license transfer or hardware failure, the Activation Key that was used on that computer must be submitted to R:BASE Technologies so we can then remove the Activation Key from our log. We will disable the Key, which will then free up that used activation. Once a key is reported to us as no longer in use and deactivated, it can no longer be used on that computer.

Product deactivation can be performed automatically from within R:BASE. To review your product information select "Help" > "Product Activation" from the Menu Bar. Here, the License Key and Activation Key for a selected product is available for review.

Product Name	Registration Number	Number of Seats	
R:BASE 11	1100007	5	
R:BASE Plugin Power Pack 11	1100007	5	
R:PDF Works 11	1100007	5	
R:Spell Checker 11	1100007	5	

If the License Key for your product is not readily available for the license transfer, select the "Copy License Key" button to send your License Key to the clipboard.

To deactivate a listed product, select it and press the "Deactivate" button. The below confirmation dialog will appear. After selecting "Yes", the product will be removed from the list.




After completing the deactivation of the product, it can be successfully reinstalled and activated.

# Part IV

### 4 Using R:Twain2PDF

#### 4.1 User Interface

The easy-to-use interface is simple yet very powerful. The menu or toolbar can be used to acquire images from your computer or from a TWAIN/scanner device.



#### 4.1.1 Tool Bar

Button	Description
~	Creates a new project and clears all current items in the work space
	Adds images to the work space
- <b>-</b>	Edits the selected image in the work space
	Deletes the selected item from the work space
<b>5</b>	Launches the <u>Select Source</u> dialog to select available TWAIN sources
-	Initiates the available scanner to scan images
- <u>1</u> 2	Saves the current work space project to a PDF document
1	Compresses the image size using the "Flate" or "Jpeg" method

	Launches the <u>PDF Document Settings</u> dialog to assign information, security, etc.
•	Launches the R:Twain2PDF Help
1	Displays product information, like version

#### 4.1.2 Add/Delete Images

#### Add Images

To add images to the work space, select the "Add Images" button from the  $\underline{\text{Tool Bar}}$ , browse for your image(s), and select OK.

#### **Edit Images**

To edit an image displayed in the work space, select the specific image, then click on the "Edit Image" button from the <u>Tool Bar</u>, The selected image may also be double clicked to open the image editor.

#### **Delete Images**

To delete images from the work space, click on the image you want removed from the work space and select the "Delete Images" button from the <u>Tool Bar</u>.

#### 4.1.3 Select Source

To acquire images to the work space from a selected source, select the "Select Source..." button from the <u>Tool Bar</u>. A dialog will be displayed with a list of TWAIN sources.

#### 4.1.4 Image Compression

**Flate** - Text data in the PDF is compressed and images retain original compression. File size and quality is determined by the original image.

**Jpeg** - a lossy compression algorithm that has been conceived to reduce the file size of natural, photographic-like true-color images as much as possible without affecting the quality of the image.

#### 4.1.5 PDF Document Properties

The PDF Document Properties allow you to add document information to the PDF output.

#### 4.1.5.1 General

*Title* - title of document *Subject* - subject of document *Author* - author of document *Keywords* - keywords of document *Creator* - creator of document *Producer* - producer of document (read only)

Open After Save - enables/disables opening the document after it is saved

DF Docum	nent S	ettings	>
General S	Securi	ty View	
Docum	nent Ir	nformation	
	Title:	No Title	
Sul	bject:	None	
Author: R:BASE User		R:BASE User	
Keyw	ords:	R:Twain2PDF	
Cre	eator:	R:Twain2PDF 11	
Prod	lucer:		
🕑 Open	Alter	Save	

#### 4.1.5.2 Security

Encrypt Document - enables/disables encryption Owner Password - owner password for the document Confirm Owner Password - confirmation of owner password for document User Password - user password for document Confirm User Password - confirmation of user password Encryption Level - encryption level option for 40 bit, 128 bit, 128 bit AES, and 256 bit AES

#### **User Permissions**

Print - enables/disables permission to print the document Modify Structure - enables/disables permission to modify document structure Copy Information - enables/disables permission to copy information from the document Modify Annotation - enables/disables permission to modify annotation

DF Docume	ent Settings		>
General S	ecurity View		
Encry	pt Document		
	Owner Password		
Confirm	Owner Password:		
	User Password:		
Confi	m User Password:		
Encryp	tion Level	. G <del>.</del>	
O 40 b	pit	128 bit AES	
0 128	bit	🔾 256 bit AES	
User P	ermissions		
🗌 Pri	nt		
	odify Structure		
	py Information		
	odify Annotation		

#### 4.1.5.3 View

*Page Layout* - options for page layout. See <u>PDF PAGE LAYOUT</u>. *Page Mode* - options for page mode. See <u>PDF PAGE MODE</u>.

#### **Viewer Preferences**


Hide Toolbars - hides/displays toolbars Hide Menu Bar - hides/displays the Menu Bar Hide Window UI - hides/displays the Window User Interface Fit Window - hides/displays the "Fit Window" button Center Window - hides/displays the "Center Window" button

OF Document Settings	
General Security View	
Page Layout:	Page Mode:
Single Page 🛛 🗸 🗸	None ~
Viewer Preferences	
<ul> <li>Hide Toolbars</li> <li>Hide Menu Bar</li> <li>Hide Window UI</li> <li>Fit Window</li> <li>Center Window</li> </ul>	
	OK Cancel

#### 4.1.6 R:Twain2PDF Image Editor

The R:Twain2PDF Image Editor provides many advanced features to manage and manipulate images for your R:BASE data.

To launch the image editor, double click an image after it is added to R:Twain2PDF.



#### 4.1.6.1 Menu Bar

#### File

- Print prints the current document to the default printer
- Printer Setup... opens the Print Setup dialog for changing page specific settings

#### Edit

- Undo undoes the last change made
- Copy copies the currently selected image
- Paste New Image inserts or pastes the currently cut or copied image
- Copy Selection copies the current selection
- Paste into Selection replaces the contents of the selection with the clipboard data
- *Crop to Selection* deletes everything except the selection and reduces the image size to the length and width of the selection

#### View

- Anti Aliased makes diagonal edges appear smoother by setting pixels near the edge to intermediate colors according to where the edge crosses them
- Centered centers the document in the middle of the screen
- Mouse Mode changes the mouse mode for image editing
- Actual Size displays the image at its actual size
- *Fit Width* fits the image into the window width

- *Fit Height* fits the image into the window height
- *Fit to Page* fits the image within the page

#### Image

- Rotate rotates an image around its center point
- Flip flips an image vertically or horizontally
- Negative replaces each pixel color with its opposite on the color wheel
- Smooth applies smoothing to the pixels at edges and corners
- *Sharpen* increases the contrast between adjacent pixels by lightening the light pixels and darkening the dark pixels
- Brightness lightens the image
- *Contrast* changes the amount of shading between areas
- Gamma... opens the Gamma dialog box to adjust the mid tones and color balance of an image
- Edge Detection marks the points at which the intensity changes sharply
- *Emboss* highlights the areas of contrast with black or white pixels and colors the low contrast areas a medium grey
- Convert to Gray converts the image to gray colors
- Format Conversion... displays the Format Conversion dialog
- *Resize* changes the size of the image

#### Format Conversion

The following color conversion options are available for the displayed image:

- Black and White
- 16 Shades of Gray
- 256 Shades of Gray
- 16 Colors
- 256 Colors
- Floyd Steinberg Dither enhances the image by looking at the current pixel color and retrieving the closest values from the palette. These colors are then distributed to the pixel areas below and to the right of the original pixel.
- Quantize reduces the number of colors in an image

#### 4.2 Command Syntax

#### Syntax:

PLUGIN RTwain2PDF vResult | Parameters

#### Where:

vResult is the text variable to return the status, such as 'OK' or the exact -ERROR- message

#### **Parameters:**

Parameter	Value	Description
SHOW_WINDOW	ON OFF	shows/hides the R:TWain2PDF dialog window
OUTPUT_FILE	value	PDF file name
OUTPUT_FORMAT	SINGLE_PDF	enables the creation of one PDF file per image
INPUT_FILE	value	Specifies the Input text file name. The order in which the path and "SCANIMAGE" parameters are specified is how they will appear in the R:Twain2PDF list, and then in the PDF output. If the line contains the text "SCANIMAGE", the scanner item will be scanned and put into image list. Example list

would be the following:           c:\Files\File1.JPG           c:\Files\File3.JPG           c:\Files\File3.JPG           SCANTMAGE           c:\Files\File3.JPG           SCANTMAGE           OPEN_AFTER_SAVE           ON           Specifies the if the PDF file is           IMAGE_COMPRESSION_TYPE           PLATE           Specifies the image compression           JPEG           TUPE           PDF_TITLE           value           specifies the PDF file subject           PDF_AUTHOR           value           specifies the PDF file subject           PDF_CREATOR           value         specifies the PDF file subject           PDF_CREATOR           value         specifies the PDF file subject           PDF_CREATOR           value         specifies the PDF file layout type           OneColumn           TwoColumnLeft           TwoColumnLeft           TwoColumnLeft           TwoColumnLeft           TwoColumnLeft           TwoColumnLeft           TwoColumnLeft           PDF_HIDE_MENUBAR           ON         shows/hides the PDF file toollbar			
e:\Pilea\Pile3.JPG           c:\Pilea\Pile3.JPG           sCANIMAGE           c:\Pilea\Pile3.JPG           sCANIMAGE           c:\Pilea\Pile3.JPG           sCANIMAGE           c:\Pilea\Pile3.JPG           SCANIMAGE           OPEN_AFTER_SAVE           ON         specifies the if the PDF file is           JAMAGE_COMPRESSION_TYPE         FLATE           Specifies the image compression         JPEG           DPF_SUBJECT         value           specifies the PDF file subject         specifies the PDF file subject           PDF_SUBJECT         value           specifies the PDF file subject         name           PDF_CREATOR         value           specifies the PDF file subject         name           PDF_CREATOR         value           Specifies the PDF file avout type           One Column_Eft         fwcColumnLeft           fwcColumnLeft         fwcColumnLeft           fwcColumnLeft         specifies the PDF file toolbar           OFF         specifies the PDF file toolbar           OFF         memubar           PDF_HIDE_MENUBAR         ON           Shows/hides the PDF file toff it the           OFF         memubar			to load images and to scan items would be the following:
e:\Pilea\Pile3.JPG           c:\Pilea\Pile3.JPG           sCANIMAGE           c:\Pilea\Pile3.JPG           sCANIMAGE           c:\Pilea\Pile3.JPG           sCANIMAGE           c:\Pilea\Pile3.JPG           SCANIMAGE           OPEN_AFTER_SAVE           ON         specifies the if the PDF file is           JAMAGE_COMPRESSION_TYPE         FLATE           Specifies the image compression         JPEG           DPF_SUBJECT         value           specifies the PDF file subject         specifies the PDF file subject           PDF_SUBJECT         value           specifies the PDF file subject         name           PDF_CREATOR         value           specifies the PDF file subject         name           PDF_CREATOR         value           Specifies the PDF file avout type           One Column_Eft         fwcColumnLeft           fwcColumnLeft         fwcColumnLeft           fwcColumnLeft         specifies the PDF file toolbar           OFF         specifies the PDF file toolbar           OFF         memubar           PDF_HIDE_MENUBAR         ON           Shows/hides the PDF file toff it the           OFF         memubar			
c:\Piles\Pile3.JPG           SCATIMAGE           c:\Piles\Pile4.JPG           c:\Piles\Pile4.JPG           c:\Piles\Pile4.JPG           COPEN_AFTER_SAVE         ON           Specifies the if the PDF file is           IMAGE_COMPRESSION_TYPE         FLATE           DPF_subject         value           Specifies the PDF file subject           PDF_SUBJECT         value           Specifies the PDF file subject           PDF_AUTHOR         value           specifies the PDF file subject           PDF_CREATOR         value           Specifies the PDF file layout type           OREColumnLeft         TwoColumnLeft           TwoColumnRight         Shows/hides the PDF file toolbar           PDF_HIDE_TOOLBAR         ON           Shows/hides the PDF file toolbar         OFF           PDF_HIDE_MODWUI         ON           OFF         window           PDF_CENTER_WINDOW         ON           OFF         window           PDF_USUBAR         ON           Specifies the PDF file off window           PDF_HIDE_TOOLBAR         ON           Shows/hides the PDF file toolbar         OFF           PDF_HIDE_WINDOWUI         ON <t< td=""><td></td><td></td><td></td></t<>			
SCANIMAGE         SCANIMAGE           0*1Y11e4-VPG         0*1Y11e4-VPG           0PEN_AFTER_SAVE         ON         Specifies the if the PDF file is           0PEN_AFTER_SAVE         OFF         launched after saving           1MAGE_COMPRESSION_TYPE         FLATE         specifies the image compression           0PE_TITLE         value         specifies the PDF file title           0PF_AUTHOR         value         specifies the PDF file woird:           0PF_KEVWORDS         value         specifies the PDF file bubject           0PF_CREATOR         value         specifies the PDF file layout type           0PF_CREATOR         None         specifies the PDF file layout type           VBC_OlumnLeft         TwoColumnLeft         file Column           FUISCreen         ON         shows/hides the PDF file toolbar           0PF_HIDE_MENUBAR         ON         shows/hides the PDF file toolbar           0PF_HIDE_MENUBAR         ON         shows/hides the PDF file tool file within           0PF_POTECTION_ENABLED         ON			
c:\Piles\File3.JPG           c:\Piles\File3.JPG           c:\Piles\File3.JPG           CPEN_AFTER_SAVE         ON           Specifies the if the PDF file is           IMAGE_COMPRESSION_TYPE         FLATE           JPEG         type           DPT_TITLE         Value           Specifies the PDF file subject           PDF_SUBJECT         value           Specifies the PDF file subject           PDF_AUTHOR         value           Specifies the PDF file subject           PDF_CREATOR         value           Specifies the PDF file subject           PDF_CREATOR         value           Specifies the PDF file subject           PDF_CREATOR         value           Specifies the PDF file advort specifies           name         specifies the PDF file advort specifies           PDF_PAGE_LAYOUT         SinglePage           OneColumn         name           TwoColumnRight         specifies the PDF file specifies           PDF_HIDE_MODE         None           UseOutines         shows/hides the PDF file           UseOutines         shows/hides the PDF file           UseOutines         shows/hides the PDF file           DPF_HIDE_MENUBAR         ON			
c:\Files\File5.JPG           OPEN_AFTER_SAVE         ON           Specifies the if the PDF file is launched after saving           IMAGE_COMPRESSION_TYPE         FLATE           Specifies the image compression JPEG         type           PDF_TITLE         value         specifies the PDF file title           PDF_SUBJECT         value         specifies the PDF file subject           PDF_AUTHOR         value         specifies the PDF file subject           PDF_CREATOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file ayout type           OneColumn         file creator         name           PDF_PAGE_MODE         None         specifies the PDF file ayout type           UseofhumSt         fullScreen         shows/hides the PDF file toolbar           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar           OFF         menubar         OPF           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file tof it the           PDF_FILT_WINDOW         ON         specifies the PDF file on the           PDF_PROTECTION_ENABLED         ON         enables/disables password			
CANTMAGE           OPEN_AFTER_SAVE         ON         specifies the if the PDF file is launched after saving           IMAGE_COMPRESSION_TYPE         FLATE         specifies the if the PDF file is by performed after saving           IMAGE_COMPRESSION_TYPE         FLATE         specifies the PDF file is by performed after saving           PDF_TITLE         value         specifies the PDF file is by performed after saving           PDF_SUBJECT         value         specifies the PDF file author name           PDF_AUTHOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file layout type           OneColumnLeft         mame         specifies the PDF file aventor           TwoColumnRight         specifies the PDF file aventor         specifies the PDF file aventor           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar           OFF         menubar         OFF         menubar           PDF_FILE_WINDOWUI         ON         specifies the PDF file to fit the           OFF         window         specifies the PDF file         file to file           PDF_CENTE_WINDOW         ON         specifies the PDF file         file to filt within			
OPEN_AFTER_SAVE         ON         specifies the if he DP File is launched after saving           IMAGE_COMPRESSION_TYPE         FLATE         specifies the image compression type           PDF_TITLE         value         specifies the PDF file subject           PDF_SUBJECT         value         specifies the PDF file subject           PDF_AUTHOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file layout type           OneColumn TwoColumnLeft         TwoColumnLeft         specifies the PDF file bage mode           UseThumbs         shows/hides the PDF file toolbar         oFF           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar           OFF         menubar         OFF         menubar           PDF_FILE_WINDOWUI         ON         specifies the PDF file to file toft within           OFF         window         Specifies the PDF file offile offile to file within           PDF_CENTE_WINDOW         ON         specifies the PDF file           PDF_FIL_WINDOW         ON<			c:\Files\File5.JPG
OFF         launched after saving           IMAGE_COMPRESSION_TYPE         FLATE         specifies the image compression           JPEG         type         specifies the PDF file title           PDF_SUBJECT         value         specifies the PDF file subject           PDF_AUTHOR         value         specifies the PDF file author           name         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file keywords           PDF_PAGE_LAYOUT         SinglePage         opecifies the PDF file layout type           OneColumn         TwoColumnLeft         twoColumnRight           PDF_PAGE_MODE         None         useOutines         useOutines           UseOutines         useOutines         useOutines         useOutines           UseOutines         ofF         menubar         PDF           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file to fit within           OFF         menubar         PDF         file to fit within           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file to fit within           OFF         menubar         PDF         file to fit within           OFF         m			SCANIMAGE
JPEG         type           DPF_TITLE         value         specifies the PDF file subject           PDF_SUBJECT         value         specifies the PDF file author           name         specifies the PDF file author         name           PDF_KEYWORDS         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file layout type           OneColumnLeft         TwoColumnRight         specifies the PDF file page mode           VseThUBE_TOOLBAR         ON         shows/hides the PDF file toolbar           OFF         menubar         pecifies the PDF file toolbar           OFF         menubar         pecifies the PDF file toolbar           OFF         window         Specifies the PDF file to fit the           PDF_IDE_WINDOW         ON         specifies the PDF file to fit thin           OFF         window         specifies the PDF file to fit thin           PDF_PROTECTION_ENABLED         ON <t< td=""><td>OPEN_AFTER_SAVE</td><td>-</td><td></td></t<>	OPEN_AFTER_SAVE	-	
PDF_TITLE       value       specifies the PDF file title         PDF_SUBJECT       value       specifies the PDF file author         PDF_AUTHOR       value       specifies the PDF file author         PDF_KEYWORDS       value       specifies the PDF file keywords         PDF_CREATOR       value       specifies the PDF file keywords         PDF_AGE_LAYOUT       SinglePage       specifies the PDF file ayout type         OneColumnLeft       TwoColumnLeft       mame         TwoColumnLeft       TwoColumnLeft       mame         PDF_HIDE_TOOLBAR       ON       shows/hides the PDF file toolbar         OFF       menubar       OFF         PDF_HIDE_WINDOWUI       ON       specifies the PDF file to fit the         OFF       window       specifies the PDF file to fit within         PDF_PROTECTION_ENABLED       ON       specifies the PDF file offic to fit within         PDF_PROTECTION_ENABLED       ON       enables/disables password         PDF_USER_PASSWORD       value       specifies the PDF file owner	IMAGE_COMPRESSION_TYPE		specifies the image compression
PDF_SUBJECT         value         specifies the PDF file subject           PDF_AUTHOR         Value         specifies the PDF file author           name         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file layout type           OneColumnIn         TwoColumnRight         specifies the PDF file layout type           PDF_PAGE_MODE         None         specifies the PDF file page mode           UseOutines         UseOutines         specifies the PDF file toolbar           PDF_HIDE_MODBAR         ON         shows/hides the PDF file           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file           PDF_HIDE_MINDOWUI         ON         shows/hides the PDF file toolbar           OFF         window         OFF         menubar           PDF_PROTECTION_ENABLED         ON         specifies the PDF file to fit the window           PDF_PROTECTION_ENABLED         ON         specifies the PDF file construction for PDF file           PDF_PROTECTION_ENABLED         ON         specifies the PDF file onser           PDF_VERE_PASSWORD         value         specifies the PDF file onser<		JPEG	
PDF_AUTHOR         value         specifies the PDF file author name           PDF_KEYWORDS         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file creator name           PDF_PAGE_LAYOUT         SinglePage OneColumn TwoColumnLeft         specifies the PDF file layout type OneColumn TwoColumnLeft           PDF_PAGE_MODE         None         specifies the PDF file page mode UseOutlines         specifies the PDF file page mode           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar OFF         shows/hides the PDF file           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file toolbar OFF         oFF           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file to fit the window         oFF           PDF_CENTER_WINDOW         ON         specifies the PDF file to fit within OFF         oFF           PDF_PROTECTION_ENABLED         ON         enables/disables password           PDF_ROTECTION_ENABLED         ON         enables/disables password           PDF_VER_PASSWORD         value         specifies the PDF file user password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file           OFF         user print permissions         ofF           PDF_PERMISSIONS_MODIFY_ANNOTATI ION         enables/disable	PDF_TITLE	value	specifies the PDF file title
name           PDF_KEYWORDS         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file creator           name         name         specifies the PDF file layout type           DPF_PAGE_LAYOUT         SinglePage         specifies the PDF file layout type           OneColumn         TwoColumnRight         specifies the PDF file page mode           UseOutlines         UseThumbs         specifies the PDF file page mode           UseThumbs         fullScreen         shows/hides the PDF file toolbar           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file           PDF_HIDE_MINDOWUI         ON         shows/hides the PDF file to filt within           OFF         window         Specifies the PDF file to fit within           PDF_CENTER_WINDOW         ON         specifies the PDF file owner           PDF_PROTECTION_ENABLED         ON         enables/disables password           PDF_VER_PASSWORD         value         specifies the PDF file owner           Password         Specifies the PDF file owner         password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file           PDF_PERMISSIONS_MODIFY_ANNOTATI         ON         enables/disables the PDF file           OFF	PDF_SUBJECT	value	specifies the PDF file subject
name           PDF_KEYWORDS         value         specifies the PDF file keywords           PDF_CREATOR         value         specifies the PDF file creator           name         name         specifies the PDF file layout type           DPF_PAGE_LAYOUT         SinglePage         specifies the PDF file layout type           OneColumn         TwoColumnRight         specifies the PDF file page mode           UseOutlines         UseThumbs         specifies the PDF file page mode           UseThumbs         fullScreen         shows/hides the PDF file toolbar           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file           PDF_HIDE_MINDOWUI         ON         shows/hides the PDF file to filt within           OFF         window         Specifies the PDF file to fit within           PDF_CENTER_WINDOW         ON         specifies the PDF file owner           PDF_PROTECTION_ENABLED         ON         enables/disables password           PDF_VER_PASSWORD         value         specifies the PDF file owner           Password         Specifies the PDF file owner         password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file           PDF_PERMISSIONS_MODIFY_ANNOTATI         ON         enables/disables the PDF file           OFF	PDF AUTHOR	value	
PDF_CREATOR         value         specifies the PDF file creator name           PDF_PAGE_LAYOUT         SinglePage OneColumn TwoColumnRight         specifies the PDF file layout type           PDF_PAGE_MODE         None UseOutines UseThumbs         specifies the PDF file page mode UseOutines UseThumbs           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar OFF           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file menubar           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file UI           OFF         OFF         window           PDF_FIT_WINDOWUI         ON         specifies the PDF file to fit the window           PDF_CENTER_WINDOW         ON         specifies the PDF file to fit within OFF           PDF_PROTECTION_ENABLED         ON         enables/disables password protection for PDF file           PDF_OWNER_PASSWORD         value         specifies the PDF file user password           PDF_VER_PASSWORD         value         specifies the PDF file user password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file user permissions           PDF_PERMISSIONS_MODIFY_STRUCTUR ON         ON         enables/disables the PDF file user permissions to change the annotation           PDF_PERMISSIONS_MODIFY_STRUCTUR OFF         ON         enables/disables the PDF file user permissions to copy sel			
PDF_CREATOR         value         specifies the PDF file creator name           PDF_PAGE_LAYOUT         SinglePage OneColumn TwoColumnRight         specifies the PDF file layout type           PDF_PAGE_MODE         None UseOutines UseThumbs         specifies the PDF file page mode UseOutines UseThumbs           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar OFF           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file menubar           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file UI           OFF         OFF         window           PDF_FIT_WINDOWUI         ON         specifies the PDF file to fit the window           PDF_CENTER_WINDOW         ON         specifies the PDF file to fit within OFF           PDF_PROTECTION_ENABLED         ON         enables/disables password protection for PDF file           PDF_OWNER_PASSWORD         value         specifies the PDF file user password           PDF_VER_PASSWORD         value         specifies the PDF file user password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file user permissions           PDF_PERMISSIONS_MODIFY_STRUCTUR ON         ON         enables/disables the PDF file user permissions to change the annotation           PDF_PERMISSIONS_MODIFY_STRUCTUR OFF         ON         enables/disables the PDF file user permissions to copy sel	PDF KEYWORDS	value	
PDF_PAGE_LAYOUT         SinglePage OneColumn TwoColumnLeft         specifies the PDF file layout type OneColumnLeft           PDF_PAGE_MODE         None UseOutines UseThumbs         specifies the PDF file page mode UseThumbs           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar OFF           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file toolbar OFF           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file to fit the Window           PDF_CENTER_WINDOW         ON         specifies the PDF file to fit within OFF           PDF_PROTECTION_ENABLED         ON         enables/disables password           PDF_USER_PASSWORD         value         specifies the PDF file owner password           PDF_USER_PASSWORD         value         specifies the PDF file owner password           PDF_KEY_LENGTH         40         specifies the PDF file owner password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file OFF           OFF         user permissions to change the annotation         off           PDF_PERMISSIONS_MODIFY_ANNOTATI ON         enables/disables the PDF file oFF         user permissions to change the annotation           PDF_PERMISSIONS_COPY         ON         enables/disables the PDF file user permissions to copy selected text           PDF_PERMISSIONS_COPY         ON         enables/disables	PDF CREATOR		specifies the PDF file creator
PDF_PAGE_LAYOUT       SinglePage OneColumn TwoColumnLeft TwoColumnRight       specifies the PDF file layout type         PDF_PAGE_MODE       None UseOutlines UseOutlines UseThumbs FullScreen       specifies the PDF file page mode         PDF_HIDE_TOOLBAR       ON       shows/hides the PDF file toolbar OFF         PDF_HIDE_MENUBAR       ON       shows/hides the PDF file         PDF_HIDE_WINDOWUI       ON       shows/hides the PDF file UI         OFF       window       specifies the PDF file to fit the         PDF_FIT_WINDOW       ON       specifies the PDF file to fit within         PDF_CENTER_WINDOW       ON       specifies the PDF file owner         PDF_PROTECTION_ENABLED       ON       enables/disables password         PDF_USER_PASSWORD       value       specifies the PDF file owner         PDF_VER_PASSWORD       value       specifies the PDF file owner         PDF_KEY_LENGTH       40       specifies the PDF file encrypted         PDF_PERMISSIONS_MODIFY_ANNOTATI       ON       enables/disables the PDF file         OFF       user print permissions to change the annotation       omation         PDF_PERMISSIONS_MODIFY_STRUCTUR       ON       enables/disables the PDF file         OFF       User Interface       OFF       user permissions to copy         Selected text       SH			
OneColumn TwoColumnLeft TwoColumnRight         Addition           PDF_PAGE_MODE         None         specifies the PDF file page mode           UseThumbs         FullScreen         Shows/hides the PDF file toolbar           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file           PDF_FIT_WINDOW         ON         specifies the PDF file to fit the           PDF_CENTER_WINDOW         ON         specifies the PDF file to fit within           OFF         window         OFF           PDF_CENTER_WINDOW         ON         specifies the PDF file owner           PDF_ONTECTION_ENABLED         ON         enables/disables password           PDF_OWNER_PASSWORD         value         specifies the PDF file owner           PASSWORD         value         specifies the PDF file owner           PASSWORD         value         specifies the PDF file owner           PDF_VER_LENGTH         40         specifies the PDF file           PDF_PERMISSIONS_MODIFY_ANNOTATI         ON         enables/disables the PDF file           OFF         user print permissions to change the annotation         annotation           PDF_PERMISSIONS_MODIFY_	PDF PAGE LAYOUT	SinglePage	
TwoColumnRight           PDF_PAGE_MODE         None           PDF_PAGE_MODE         None           UseOutlines         Specifies the PDF file page mode           UseOutlines         UseOutlines           UseOutlines         Shows/hides the PDF file toolbar           OFF         ON           PDF_HIDE_TOOLBAR         ON           PDF_HIDE_MENUBAR         ON           OFF         menubar           PDF_HIDE_WINDOWUI         ON           OFF         window           PDF_FIT_WINDOW         ON           OFF         window           PDF_CENTER_WINDOW         ON           OFF         window           PDF_PROTECTION_ENABLED         ON           OFF         protection for PDF file           PDF_OWNER_PASSWORD         value           Specifies the PDF file owner         password           PDF_USER_PASSWORD         value           PDF_KEY_LENGTH         40           Specifies the PDF file         user print permissions           PDF_PERMISSIONS_MODIFY_ANNOTATI         ON           OFF         user print permissions to change the annotation           PDF_PERMISSIONS_MODIFY_STRUCTUR         ON           PDF_PERMISSIONS_			
TwoColumnRightPDF_PAGE_MODENoneSpecifies the PDF file page modeUseOutlinesUseThumbsSpecifies the PDF file page modePDF_HIDE_TOOLBARONShows/hides the PDF file toolbarPDF_HIDE_MENUBARONShows/hides the PDF filePDF_HIDE_WINDOWUIONShows/hides the PDF file UIOFFOFFmenubarPDF_FIT_WINDOWONSpecifies the PDF file to fit the windowPDF_CENTER_WINDOWONSpecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDONenables/disables passwordPDF_USER_PASSWORDvalueSpecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_PREMISSIONS_PRINTONenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI OFFONenables/disables the PDF file user print permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EONenables/disables the PDF file user printsions to modify the structurePDF_PERMISSIONS_COPYONenables/disables the PDF file user primissions to copy selected textSHOW_SCANNER_UIONenables/disables the Scanner OFFDPIValueSpecifies the resolution for the			
PDF_PAGE_MODE         None UseOutlines UseThumbs FullScreen         specifies the PDF file page mode           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file UI           PDF_FIDE_WINDOWUI         ON         specifies the PDF file to fit the window           PDF_FIT_WINDOW         ON         specifies the PDF file to fit the window           PDF_FORTECTION_ENABLED         ON         enables/disables password           OFF         protection for PDF file protection for PDF file opF         password           PDF_USER_PASSWORD         value         specifies the PDF file owner password           PDF_VESE_PASSWORD         value         specifies the PDF file owner password           PDF_VESE_PASSWORD         value         specifies the PDF file owner password           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file oFF           OFF         user print permissions         protection for PDF file oFF           PDF_PERMISSIONS_MODIFY_ANNOTATI ON         enables/disables the PDF file oFF         user permissions to change the annotation           PDF_PERMISSIONS_COPY         ON         enables/disables the PDF file oFF         user printsions to copy selected text			
UseOutlines UseThumbs FullScreen         Shows/hides the PDF file toolbar           PDF_HIDE_TOOLBAR         ON         shows/hides the PDF file toolbar           PDF_HIDE_MENUBAR         ON         shows/hides the PDF file           PDF_HIDE_WINDOWUI         ON         shows/hides the PDF file UI           PDF_FIT_WINDOW         ON         specifies the PDF file to fit the window           PDF_CENTER_WINDOW         ON         specifies the PDF file to fit within OFF           PDF_PROTECTION_ENABLED         ON         enables/disables password           PDF_OWNER_PASSWORD         value         specifies the PDF file           PDF_USER_PASSWORD         value         specifies the PDF file encrypted have password           PDF_LENGTH         40         specifies the PDF file encrypted have permissions           PDF_PERMISSIONS_PRINT         ON         enables/disables the PDF file oFF           PDF_PERMISSIONS_MODIFY_ANNOTATI ON         ON         enables/disables the PDF file user permissions to change the annotation           PDF_PERMISSIONS_MODIFY_STRUCTUR E         ON         enables/disables the PDF file USER permissions to copy selected text           SHOW_SCANNER_UI         ON         enables/disables the PDF file user permissions to copy selected text	PDE PAGE MODE		specifies the PDF file page mode
UseThumbs FullScreenPDF_HIDE_TOOLBARON OFFPDF_HIDE_MENUBARON OFFPDF_HIDE_MENUBARON OFFPDF_HIDE_WINDOWUION OFFPDF_HIDE_WINDOWUION OFFPDF_FIT_WINDOWON OFFPDF_CENTER_WINDOWON OFFPDF_PROTECTION_ENABLEDON OFFPDF_OWNER_PASSWORDvalue protection for PDF file owner passwordPDF_KEY_LENGTH40 OFFPDF_PRATISSIONS_PRINTON OFFPDF_PRATISSIONS_MODIFY_ANNOTATI ON OFFON enables/disables the PDF file offfPDF_PRATISSIONS_MODIFY_STRUCTUR ON OFFON enables/disables the PDF file offfPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_PRATISSIONS_COPYON OFFPDF_DERMISSIONS_COPYON OFFPDF USER_UION OFFPDF USER_VINESCANNER_UION OFFON OFFenables/disables the Scanner USEPOFFUSEP InterfaceDPIValueSHOW_SCANNER_UION OFFON OFFenables/disables the Scanner USEP InterfaceDPIValueSpecifies the resolution for the </td <td></td> <td></td> <td>specifies the PDP file page filode</td>			specifies the PDP file page filode
FullScreenPDF_HIDE_TOOLBARON OFFshows/hides the PDF file toolbarPDF_HIDE_MENUBARON OFFshows/hides the PDF file menubarPDF_HIDE_WINDOWUION OFFshows/hides the PDF file UI OFFPDF_FIT_WINDOWON OFFspecifies the PDF file to fit the windowPDF_CENTER_WINDOWON OFFspecifies the PDF file to fit within the centerPDF_PROTECTION_ENABLEDON OFFenables/disables password oFFPDF_OWNER_PASSWORDvalue valuespecifies the PDF file owner passwordPDF_VER_PASSWORDvalue valuespecifies the PDF file encrypted key lengthPDF_KEY_LENGTH40 OFFspecifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINT ON PDF_PERMISSIONS_MODIFY_ANNOTATI ON EON enables/disables the PDF file user print permissions ofFPDF_PERMISSIONS_MODIFY_STRUCTUR PDF_PERMISSIONS_COPYON OFF OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_COPY OFFON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UI OFFON OFFenables/disables the Scanner User InterfacePDIValuespecifies the resolution for the			
PDF_HIDE_TOOLBARON OFFshows/hides the PDF file toolbar OFFPDF_HIDE_MENUBARON OFFshows/hides the PDF file menubarPDF_HIDE_WINDOWUION OFFshows/hides the PDF file UI OFFPDF_FIT_WINDOWON OFFspecifies the PDF file to fit the windowPDF_CENTER_WINDOWON OFFspecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDON OFFenables/disables password PDF_OWNER_PASSWORDPDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_KEY_LENGTH40 128specifies the PDF file encrypted lassles the PDF file oFFPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file oFFPDF_PERMISSIONS_MODIFY_ANNOTATION OFFenables/disables the PDF file user permissionsPDF_PERMISSIONS_MODIFY_STRUCTUR PDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_COPYON OFFon ofFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner OFFDPIValuespecifies the resolution for the			
PDF_HIDE_MENUBAROFFHow we havePDF_HIDE_MENUBARONshows/hides the PDF filePDF_HIDE_WINDOWUIONshows/hides the PDF file UIOFFOFFPDF_FIT_WINDOWONspecifies the PDF file to fit the windowPDF_CENTER_WINDOWONspecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDONenables/disables password OFFPDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file oFFPDF_PERMISSIONS_MODIFY_ANNOTATI ON ON EON enables/disables the PDF file oFFPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file oFFPDF_PERMISSIONS_COPYON OFFenables/disables the PDF file oFFPDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UI DPION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			shows/hidos the RDE file teelbar
PDF_HIDE_MENUBAR       ON       shows/hides the PDF file         PDF_HIDE_WINDOWUI       ON       shows/hides the PDF file UI         OFF       shows/hides the PDF file to fit the         PDF_FIT_WINDOW       ON       specifies the PDF file to fit the         OFF       window         PDF_CENTER_WINDOW       ON       specifies the PDF file to fit within         OFF       the center         PDF_PROTECTION_ENABLED       ON       enables/disables password         PDF_OWNER_PASSWORD       value       specifies the PDF file owner         password       password       PDF_USER_PASSWORD       value         PDF_KEY_LENGTH       40       specifies the PDF file encrypted       key length         PDF_PERMISSIONS_PRINT       ON       enables/disables the PDF file         OFF       user print permissions       permissions to change the annotation         PDF_PERMISSIONS_MODIFY_ANNOTATI       ON       enables/disables the PDF file         OFF       user permissions to change the annotation       poFF         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         OFF       user permissions to copy selected text       shows/hides the PDF file         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file <t< td=""><td>PDP_HIDL_TOOLDAR</td><td>-</td><td>shows/fildes the PDP file toolbai</td></t<>	PDP_HIDL_TOOLDAR	-	shows/fildes the PDP file toolbai
OFFmenubarPDF_HIDE_WINDOWUIONshows/hides the PDF file UIPDF_FIT_WINDOWONspecifies the PDF file to fit the oFFPDF_CENTER_WINDOWONspecifies the PDF file to fit within OFFPDF_CENTER_WINDOWONspecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDONenables/disables password protection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file encrypted tasswordPDF_KEY_LENGTH40specifies the PDF file encrypted tasswordPDF_PERMISSIONS_PRINTONenables/disables the PDF file oFFONenables/disables the PDF file oFFoFFONenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI PDF_PERMISSIONS_MODIFY_STRUCTUR PDF_PERMISSIONS_COPYONPDF_PERMISSIONS_COPYONenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_COPYONenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UIONenables/disables the Scanner OFFDPIvaluespecifies the resolution for the			shows/hidos the RDE file
PDF_HIDE_WINDOWUI       ON       Shows/hides the PDF file UI         PDF_FIT_WINDOW       ON       specifies the PDF file to fit the         OFF       window         PDF_CENTER_WINDOW       ON       specifies the PDF file to fit within         OFF       the center         PDF_PROTECTION_ENABLED       ON       enables/disables password         OFF       protection for PDF file         PDF_OWNER_PASSWORD       value       specifies the PDF file owner         PDF_USER_PASSWORD       value       specifies the PDF file encrypted         PDF_KEY_LENGTH       40       specifies the PDF file encrypted         PDF_PERMISSIONS_PRINT       ON       enables/disables the PDF file         OFF       user print permissions       PDF file         PDF_PERMISSIONS_MODIFY_ANNOTATI       ON       enables/disables the PDF file         OFF       OFF       user permissions to change the annotation         PDF_PERMISSIONS_MODIFY_STRUCTUR       ON       enables/disables the PDF file         OFF       User permissions to copy       structure         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         OFF       User Interface       OFF         SHOW_SCANNER_UI       ON       enables/disables the Scanner	FDI_HIDL_MENODAK	-	
OFFPDF_FIT_WINDOWONspecifies the PDF file to fit the OFFPDF_CENTER_WINDOWONspecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDONenables/disables password oFFPDF_OWNER_PASSWORDValuespecifies the PDF file owner passwordPDF_USER_PASSWORDValuespecifies the PDF file user passwordPDF_USER_PASSWORDValuespecifies the PDF file encrypted lasswordPDF_KEY_LENGTH40specifies the PDF file encrypted lassPDF_PERMISSIONS_PRINTONenables/disables the PDF file oFFOFFuser print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONONenables/disables the PDF file oFFOFFuser permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR PDF_PERMISSIONS_MODIFY_STRUCTUR OFFONenables/disables the PDF file oFFPDF_PERMISSIONS_COPYONenables/disables the PDF file oFFofFPDF_PERMISSIONS_COPYONenables/disables the PDF file oFFPDF_PERMISSIONS_COPYONenables/disables the PDF file oFFSHOW_SCANNER_UIONenables/disables the Scanner OFFOFFUser permissions to copy selected textSHOW_SCANNER_UIValuespecifies the resolution for the			
PDF_FIT_WINDOWON OFFspecifies the PDF file to fit the windowPDF_CENTER_WINDOWON OFFspecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDON OFFenables/disables password protection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file encrypted l28PDF_VER_LENGTH40 128specifies the PDF file encrypted l28PDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file oFFON OFFenables/disables the PDF file oFFON OFFenables/disables the PDF file oFFPDF_PERMISSIONS_MODIFY_ANNOTATI ON PDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFPDF_PERMISSIONS_COPYON OFFPDF_PERMISSIONS_COPYON OFFPDF_PERMISSIONS_COPYON OFFPDF_PERMISSIONS_COPYON OFFPDF_PERMISSIONS_COPYON OFFON Selected textSHOW_SCANNER_UI OFFON OFFON OFFenables/disables the Scanner OFFOFFUser InterfaceDPIvalueShow_SCANNER_UION OFFON OFFenables/disables the Scanner OFFOFFUser InterfaceDPIvalueONspecifies the resolution for the			shows/fildes the PDF file 01
OFFwindowPDF_CENTER_WINDOWONspecifies the PDF file to fit within OFFPDF_PROTECTION_ENABLEDONenables/disables password protection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file encrypted key lengthPDF_LSER_PASSWORDvaluespecifies the PDF file encrypted key lengthPDF_KEY_LENGTH40specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTONenables/disables the PDF file oFFONOFFuser print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONONenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EONenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYONenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UI DPIONenables/disables the Scanner OFFOFFUser InterfaceDPIvaluespecifies the resolution for the			
PDF_CENTER_WINDOWON OFFspecifies the PDF file to fit within the centerPDF_PROTECTION_ENABLEDON OFFenables/disables password protection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file encrypted 128PDF_KEY_LENGTH40 Specifies the PDF file encrypted textspecifies the PDF file encrypted textPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ON OFFON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UI OFFON OFFonables/disables the Scanner OFFOFFUser InterfaceDPIvaluespecifies the resolution for the			
OFFthe centerPDF_PROTECTION_ENABLEDONenables/disables passwordOFFprotection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file ownerPDF_USER_PASSWORDvaluespecifies the PDF file userPDF_USER_PASSWORDvaluespecifies the PDF file encryptedPDF_KEY_LENGTH40specifies the PDF file encryptedPDF_PERMISSIONS_PRINTONenables/disables the PDF fileOFFuser print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATIONenables/disables the PDF fileONOFFuser permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTURONenables/disables the PDF filePDF_PERMISSIONS_COPYONenables/disables the PDF file user permissions to copy selected textPDF_NERMISSIONS_COPYONenables/disables the PDF file user permissions to copy selected textPDF_PERMISSIONS_COPYONenables/disables the Scanner OFFOFFUser InterfaceDPIDPIvaluespecifies the resolution for the			
PDF_PROTECTION_ENABLEDON OFFenables/disables password protection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_KEY_LENGTH40 128specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ON OFFON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR PDF_PERMISSIONS_MODIFY_STRUCTUR PDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UI DFION OFFON User InterfaceDPIvaluespecifies the resolution for the	PDF_CENTER_WINDOW		
OFFprotection for PDF filePDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_KEY_LENGTH40 128specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner OFFDPIvaluespecifies the resolution for the	DDE DDATEATIAN ENADLED		
PDF_OWNER_PASSWORDvaluespecifies the PDF file owner passwordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_USER_PASSWORD40specifies the PDF file encrypted l28PDF_KEY_LENGTH40specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the	PDF_PROTECTION_ENABLED	-	
PDF_USER_PASSWORDvaluepasswordPDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_KEY_LENGTH40specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ON ON OFFON enables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			
PDF_USER_PASSWORDvaluespecifies the PDF file user passwordPDF_KEY_LENGTH40 128specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textPDF_SCANNER_UI DPION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the	PDF_OWNER_PASSWORD	value	
PDF_KEY_LENGTH40 specifies the PDF file encrypted key lengthPDF_KEY_LENGTH40 128specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			
PDF_KEY_LENGTH40 128specifies the PDF file encrypted key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ON ON PDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UI DPION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the	PDF_USER_PASSWORD	value	
128key lengthPDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textPDW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			
PDF_PERMISSIONS_PRINTON OFFenables/disables the PDF file user print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONON OFFenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EON OFFenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textPDF_SCANNER_UI DPION OFFenables/disables the Scanner User InterfacePDFValuespecifies the resolution for the	PDF_KEY_LENGTH	-	specifies the PDF file encrypted
OFFuser print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONONenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EONenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textPDW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the		128	key length
OFFuser print permissionsPDF_PERMISSIONS_MODIFY_ANNOTATI ONONenables/disables the PDF file user permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EONenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textPDW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			L
PDF_PERMISSIONS_MODIFY_ANNOTATI       ON       enables/disables the PDF file         ON       OFF       user permissions to change the annotation         PDF_PERMISSIONS_MODIFY_STRUCTUR       ON       enables/disables the PDF file         E       OFF       user permissions to modify the structure         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         VDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         VDF_SCANNER_UI       ON       enables/disables the Scanner         OFF       User Interface       DPI	PDF_PERMISSIONS_PRINT		
ONOFFuser permissions to change the annotationPDF_PERMISSIONS_MODIFY_STRUCTUR EONenables/disables the PDF file user permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			
annotation         PDF_PERMISSIONS_MODIFY_STRUCTUR       ON       enables/disables the PDF file         E       OFF       user permissions to modify the structure         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         OFF       user permissions to copy selected text         SHOW_SCANNER_UI       ON       enables/disables the Scanner         OFF       User Interface         DPI       value       specifies the resolution for the			
PDF_PERMISSIONS_MODIFY_STRUCTUR       ON       enables/disables the PDF file         E       OFF       user permissions to modify the structure         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         OFF       user permissions to copy selected text         SHOW_SCANNER_UI       ON       enables/disables the Scanner         OFF       User Interface         DPI       value       specifies the resolution for the	ON	OFF	
EOFFuser permissions to modify the structurePDF_PERMISSIONS_COPYON OFFenables/disables the PDF file user permissions to copy selected textSHOW_SCANNER_UION OFFenables/disables the Scanner User InterfaceDPIvaluespecifies the resolution for the			
structure         PDF_PERMISSIONS_COPY       ON       enables/disables the PDF file         OFF       user permissions to copy       selected text         SHOW_SCANNER_UI       ON       enables/disables the Scanner         OFF       User Interface         DPI       value       specifies the resolution for the			enables/disables the PDF file
structure       PDF_PERMISSIONS_COPY     ON OFF     enables/disables the PDF file user permissions to copy selected text       SHOW_SCANNER_UI     ON OFF     enables/disables the Scanner User Interface       DPI     value     specifies the resolution for the	E	OFF	user permissions to modify the
OFF     user permissions to copy selected text       SHOW_SCANNER_UI     ON     enables/disables the Scanner       OFF     User Interface       DPI     value     specifies the resolution for the			
OFF     user permissions to copy selected text       SHOW_SCANNER_UI     ON     enables/disables the Scanner       OFF     User Interface       DPI     value     specifies the resolution for the	PDF_PERMISSIONS_COPY	ON	enables/disables the PDF file
selected text       SHOW_SCANNER_UI     ON     enables/disables the Scanner       OFF     User Interface       DPI     value     specifies the resolution for the		OFF	
SHOW_SCANNER_UI     ON     enables/disables the Scanner       OFF     User Interface       DPI     value     specifies the resolution for the			
OFF         User Interface           DPI         value         specifies the resolution for the	SHOW SCANNER UT	ON	
DPI value specifies the resolution for the			
	DPI		
		1	

Copyright © 1982-2025 R:BASE Technologies, Inc.

		scanner options)
SOURCE_NAME	value	specifies the twain source. The value should match the value provided through the R:Twain2PDF interface when selecting "File" > "Select Source" from the menu bar
SCAN_IMAGE_COUNT	nnn	specifies the number of images to scan
SCAN_IMAGE_PAUSE_DIALOG	ON OFF	displays a pause dialog between multiple scans
FILE_NAME_VARIABLE_PREFIX	value	specifies the variable prefix for the scanned file name; and can be used when scanning multi- page documents

#### Notes:

- Each option must be separated by the pipe "|" character.
- No additional PLUGIN command parameter is required for the (ADF) automatic document feeder. ADF is available if the hardware supports it.
- ADF is automatically used if the feeder bin has contents. Otherwise, the scanner bed is used.

#### 4.3 Examples

#### 4.3.1 Example 1

- -- to scan one document to a pdf file without the
- -- R:Twain2PDF and scanner user interface,
- -- with title, subject, author, keywords and creator
- -- not launching the final result

```
PLUGIN RTwain2PDF vResult +
```

```
|OUTPUT_FILE RAM_Disclosure.PDF +
|SCAN_IMAGE_COUNT 1 +
|PDF_TITLE RAM Data Systems - Internal +
|PDF_SUBJECT Confidentiality Disclosure +
|PDF_AUTHOR Technical Services Staff +
|PDF_KEYWORDS disclosure, confidential, internal +
|PDF_CREATOR RAM Data Systems +
|SHOW_WINDOW OFF +
|SHOW_SCANNER_UI OFF +
|OPEN_AFTER_SAVE OFF
RETURN
```

#### 4.3.2 Example 2

- -- to scan two images to a pdf file without the R:Twain2PDF
- -- and scanner user interface, with the PDF toolbar, menubar
- -- and user inteface hidden launching the final result in the center

```
PLUGIN RTwain2PDF vResult +
```

```
OUTPUT_FILE ViewCenter_Clean.PDF +
SCAN_IMAGE_COUNT 2 +
SCAN_IMAGE_PAUSE_DIALOG ON +
SHOW_WINDOW OFF +
SHOW_SCANNER_UI OFF +
PDF_HIDE_TOOLBAR OFF +
```

```
| PDF_HIDE_MENUBAR OFF +
| PDF_HIDE_WINDOWUI OFF +
| PDF_CENTER_WINDOW ON +
| OPEN_AFTER_SAVE OFF
RETURN
```

#### 4.3.3 Example 3

- -- to scan one image to a pdf file without the
- -- R:Twain2PDF and scanner user interface,
- -- applying security measures and not
- -- launching the final result

```
PLUGIN RTwain2PDF vResult +
    |OUTPUT_FILE FSE_042507_108776.PDF +
    INPUT_FILE STAGE_LIST.TXT +
    SHOW_WINDOW OFF +
    SHOW_SCANNER_UI OFF +
    PDF_PROTECTION_ENABLED ON +
    PDF_OWNER_PASSWORD griffin +
    PDF_USER_PASSWORD atrebek +
    PDF_USER_PASSWORD atrebek +
    PDF_LENGTH 128 +
    PDF_PERMISSIONS_PRINT ON +
    PDF_PERMISSIONS_MODIFY_ANNOTATION OFF +
    PDF_PERMISSIONS_MODIFY_STRUCTURE OFF +
    PDF_PERMISSIONS_COPY OFF +
    |OPEN_AFTER_SAVE OFF
    RETURN
```

The contents of the STAGE\_LIST.TXT file would be something like the following:

```
C:\PHOTOS\STAGE19\Audience1.JPG
C:\PHOTOS\STAGE19\Audience2.JPG
C:\PHOTOS\STAGE19\Audience3.JPG
C:\PHOTOS\STAGE19\Audience4.JPG
C:\PHOTOS\STAGE19\Audience5.JPG
C:\PHOTOS\STAGE19\Contestants1.JPG
C:\PHOTOS\STAGE19\Contestants2.JPG
C:\PHOTOS\STAGE19\Contestants3.JPG
C:\PHOTOS\STAGE19\Contestants4.JPG
C:\PHOTOS\STAGE19\Contestants5.JPG
C:\PHOTOS\STAGE19\ATrebek1.JPG
C:\PHOTOS\STAGE19\ATrebek2.JPG
C:\PHOTOS\STAGE19\ATrebek3.JPG
C:\PHOTOS\STAGE19\ATrebek4.JPG
C:\PHOTOS\STAGE19\Jeopardy1.JPG
C:\PHOTOS\STAGE19\Jeopardy2.JPG
C:\PHOTOS\STAGE19\Jeopardy3.JPG
```

#### 4.3.4 Example 4

- -- to perform multiple scans fed from from the automatic document
- -- feeder bin to pdf files without showing the R:Twain2PDF or scanner
- -- user interface

PLUGIN RTwain2PDF vResult +

```
OUTPUT_FORMAT PDF +
OUTPUT_FILE Scan_.PDF +
OUTPUT_FORMAT SINGLE_PDF +
SCAN_IMAGE_COUNT 1 +
SHOW_WINDOW OFF +
SHOW_SCANNER_UI OFF +
OPEN_AFTER_SAVE OFF
'THEM
```

#### RETURN

No additional PLUGIN command parameter is required for the automatic document feeder. ADF is available if the hardware supports it.

Based upon the specified file name ,Scan\_.PDF, the output files will be named Scan\_xxxx.PDF, depending on the number of pages.

# Part V

### 5 Technical Support

Please read over the help documentation at least once before seeking support. We have worked very hard to make the help documentation clear and useful, but concise. It is suggested that you reread these instructions once you have become accustomed to using the software, as new uses will become apparent.

If you have further questions, and cannot find the answers in the documentation, you can obtain information from the below sources:

- Email our Technical Support Staff at: <a href="mailto:support@rbase.com">support@rbase.com</a>
- Access the R:BASE Technologies Support home page online at <a href="https://www.rbase.com/support">https://www.rbase.com/support</a>

You may be required to purchase a technical support plan. Several support plans are available to suit the needs of all users. <u>Available Technical Support Plans</u>

Please be prepared to provide the following:

- The product registration number, which is located on the invoice/order slip for the purchased product
- The type of operating system and hardware in use
- Details regarding your operating environment; such as available memory, disk space, your version
  of R:BASE, local area network, special drivers, related database structures, application files, and
  other files that are used or accessed by your application

All provide information will be used to better assist you.

R:BASE Technologies has a number of different services available for R:BASE products. As a registered user, you will receive information about new features for R:BASE and other R:BASE Technologies products. Please remember to register your software. <u>https://www.rbase.com/register/</u>

# Part VI

## 6 Useful Resources

. R:BASE Home Page:	https://www.rbase.com
. Up-to-Date R:BASE Updates:	https://www.rbaseupdates.com
. Current Product Details and Documentation:	https://www.rbase.com/rbg11
. Support Home Page:	https://www.rbase.com/support
. Product Registration:	https://www.rbase.com/register
. Official R:BASE Facebook Page:	https://www.facebook.com/rbase
. Sample Applications:	https://www.razzak.com/sampleapplications
. Technical Documents (From the Edge):	https://www.razzak.com/fte
. Education and Training:	https://www.rbase.com/training
. Product News:	https://www.rbase.com/news
. Upcoming Events:	https://www.rbase.com/events
. R:BASE Online Help Manual:	https://www.rbase.com/support/rsyntax
. Form Properties Documentation:	https://www.rbase.com/support/FormProperties.pdf
. R:BASE Beginners Tutorial:	https://www.rbase.com/support/rtutorial
. R:BASE Solutions (Vertical Market Applications):	https://www.rbase.com/products/rbasesolutions



#### 7 Feedback

#### Suggestions and Enhancement Requests:

From time to time, everyone comes up with an idea for something they'd like a software product to do differently.

If you come across an idea that you think might make a nice enhancement, your input is always welcome.

Please submit your suggestion and/or enhancement request to the R:BASE Developers' Corner Crew (R:DCC) and describe what you think might make an ideal enhancement. In R:BASE, the R:DCC Client is fully integrated to communicate with the R:BASE development team. From the main menu bar, choose "Help" > "R:DCC Client". If you do not have a login profile, select "New User" to create one.

If you have a sample you wish to provide, have the files prepared within a zip archive prior to initiating the request. You will be prompted to upload any attachments during the submission process.

Unless additional information is needed, you will not receive a direct response. You can periodically check the status of your submitted enhancement request.

If you are experiencing any difficulties with the R:DCC Client, please send an e-mail to rdcc@rbase.com.

#### **Reporting Bugs:**

If you experience something you think might be a bug, please report it to the R:BASE Developers' Corner Crew. In R:BASE, the R:DCC Client is fully integrated to communicate with the R:BASE development team. From the main menu bar, choose "Help" > "R:DCC Client". If you do not have a login profile, select "New User" to create one.

You will need to describe:

- What you did, what happened, and what you expected to happen
- The product version and build
- Any error message displayed
- The operating system in use
- Anything else you think might be relevant

If you have a sample you wish to provide, have the files prepared within a zip archive prior to initiating the bug report. You will be prompted to upload any attachments during the submission process.

Unless additional information is needed, you will not receive a direct response. You can periodically check the status of your submitted bug.

If you are experiencing any difficulties with the R:DCC Client, please send an e-mail to rdcc@rbase.com.

# Index

# - A -

activate 13, 14 activation 14 Activation Key 14, 19 ADF 27, 30 administrator 13 author 22 automatic document feeder 27, 30

# - B -

brightness 25

# - C -

command 27 Computer ID 14 contrast 25 convert to gray 25 сору 25 copyright 6 creator 22 crop 25

# - D -

deactivation 19

# - E -

edge detection 25 emboss 25 encrypt 23 example 29

# - F -

feedback 37 flate 22 flip horizontal 25 flip vertical 25 Floyd Steinberg Dither 25 format conversion 25

# - G -

gamma 25

# - | -

image 22 add 22 compression 22 delete 22 image editor 25 install 14 intro 6

# - J -

jpeg 22

# - K -

key, activation 13 key, license 13 keywords 22

# - L -

license 7, 13 License Key 14, 16, 17, 19 license transfer 19

# - N -

negative 25

# - 0 -

open 22 owner 23

# - P -

page layout 24

39

page mode 24 parameters 27 password 23 paste 25 PDF output 22 permission 13 permissions 23 PLUGIN 14, 27 16, 17 **Plugin File** print 25 printer setup 25 producer 22 PROPERTY 17

# - Q -

quantize 25

# - R -

R:Compiler 16 register 14 registration number 13 requirements 14 resize 25 rotates 25 Runtime 17

# - S -

scan 22 scanner 22 23 security sharpen 25 smooth 25 22 source subject 22 support 10, 13 syntax 27 system requirements 13

# - T -

title 22 tool bar 21 TWAIN 22

# - U -

UAC 13 Uninstall 19 user 23 User Access Control 13 user interface 21

# - V -

view 24

# - Z -

zoom 25

