

# R:Magellan 11



## Help Manual



# R:Magellan 11

## Manual

---

*by R:BASE Technologies, Inc.*

*Welcome to R:Magellan 11!*

*R:Magellan is a R:BASE Plugin for integrating powerful mapping and analysis features into your R:BASE application. Using R:Magellan with several mapping solutions, including MapPoint and Maptitude software programs, as well as Google Maps, Bing Maps, and MapQuest online services, users can provide fast geographical travel instructions for multiple locations.*


# Table of Contents

<b>Part I Introduction</b>	<b>5</b>
1 Introducing R:Magellan 11 .....	6
2 Copyrights .....	6
3 License .....	7
4 Complimentary Support .....	11
<b>Part II Installation</b>	<b>12</b>
1 System Requirements .....	13
2 Things You Will Need .....	13
3 Software Installation .....	14
4 Plugin Activation .....	14
R:BASE .....	15
R:Compiler for R:BASE .....	17
Runtime for R:BASE .....	17
<b>Part III Uninstall</b>	<b>18</b>
<b>Part IV Map Engine Comparison</b>	<b>20</b>
<b>Part V Working With MapPoint</b>	<b>22</b>
1 Map Calculation .....	24
2 Map Display .....	29
3 Printing Maps .....	30
4 Return Variables .....	31
5 Examples .....	32
Example 1 .....	32
Example 2 .....	33
Example 3 .....	35
Example 4 .....	37
Example 5 .....	37
<b>Part VI Working With Azure Maps</b>	<b>38</b>
1 Map Calculation .....	40
2 Return Variables .....	41
3 Examples .....	42
Example 1 .....	42
Example 2 .....	43
Example 3 .....	45
Example 4 .....	47

<b>Part VII Working With Google Maps</b>	<b>49</b>
1 Map Calculation .....	52
2 Return Variables .....	53
3 Examples .....	54
Example 1 .....	54
Example 2 .....	55
Example 3 .....	57
Example 4 .....	59
<b>Part VIII Working With MapQuest</b>	<b>61</b>
1 Map Calculation .....	62
2 Return Variables .....	63
3 Examples .....	64
Example 1 .....	64
Example 2 .....	65
Example 3 .....	66
<b>Part IX Find Address Utility</b>	<b>67</b>
1 Examples .....	68
<b>Part X Geocoding</b>	<b>70</b>
1 Examples .....	71
<b>Part XI Technical Support</b>	<b>73</b>
<b>Part XII Useful Resources</b>	<b>75</b>
<b>Part XIII Feedback</b>	<b>77</b>
<b>Index</b>	<b>79</b>



**Part**



# 1 Introduction

## 1.1 Introducing R:Magellan 11

R:Magellan is a R:BASE Plugin for integrating powerful mapping and analysis features into your R:BASE application. Using R:Magellan with several mapping solutions, including MapPoint and Maptitude software programs, as well as Google Maps, Azure Maps, and MapQuest online services, users can provide fast geographical travel instructions for multiple locations.

Working with addresses or Latitude and Longitude coordinates, R:Magellan will map a specified route, from start to finish, and returns values for the trip including: total distance, trip duration, driving time, driving cost, longitude and latitude for each address, the distance traveled between the addresses, the elapsed distance and the number of addresses provided. The driving cost units and price are available to calculate a driving cost for a trip. In the event an address has multiple hits or is invalid, a "Find Address" dialog will be displayed to correct the existing address or specify a different address.

With the OPTIMIZATION parameter, R:Magellan can reorder the intermediate stops on your route so that your travel time between the start and end points is the most time-efficient.

Maps and directions can be sent to your printer with many additional options like a turn-by-turn map, driving directions only, a fax-able map, including the map legend, and more. After a route is calculated, a URL is returned based on the waypoints, which can be sent by email to a driver's mobile device (with Google maps) to take advantage of GPS assisted navigation.

When launching maps, you can edit the different destination points and how they are displayed on the map. Other parameters allow you to control whether toolbars are displays, map styles, and window state. Map files can also be saved and loaded with R:Magellan. Google and Azure map display include the options to for a "Trip Information" bar, which contains details for each waypoint, and a "Navigation" bar which contains details for each waypoint. The Navigation bar will only display if the Trip Information bar is displayed.

A Find Address utility is available to check if an address can be located. The search can be performed with an address or Latitude and Longitude coordinates. An address search may also perform in "silent" mode to hide the "Find Address" dialog.

R:Magellan supports geocoding to find latitude and longitude coordinate geographic data from a provided street address. The plugin also provides reverse geocoding where an approximate address is returned with given latitude and longitude coordinates.

Your mapping solution software or online solution must be installed and/or configured accordingly before using the R:Magellan Plugin.

## 1.2 Copyrights

Information in this document, including URL and other Internet web site references, is subject to change without notice. The example companies, individuals, products, organizations and events depicted herein are completely fictitious. Any similarity to a company, individual, product, organization or event is completely unintentional. R:BASE Technologies, Inc. shall not be liable for errors contained herein or for incidental consequential damages in connection with the furnishing, performance, or use of this material. This document contains proprietary information, which is protected by copyright. Complying with all applicable copyright laws is the responsibility of the user. Without limiting the rights under copyright, no part of this document may be reproduced, stored in or introduced into a retrieval system, or transmitted in any form or by any means (electronic, mechanical, photocopying, recording, or otherwise), or for any purpose, without the express written consent of R:BASE Technologies, Inc. We reserve the right to make changes from time to time in the contents hereof without obligation to notify any person of such revision or changes. We also reserve the right to change the specification without notice and may therefore not coincide with the contents of this document. The manufacturer assumes no responsibilities with regard to the performance or use of third party products.

Products that are referred to in this document may be either trademarks and/or registered trademarks of the respective owners. The publisher and the author make no claim to these trademarks.

The software described in this document is furnished under a license agreement. The software may be used or copied only in accordance with the terms of that agreement. Any unauthorized use or duplication of the software is forbidden.

R:BASE Technologies, Inc. may have patents, patent applications, trademarks, copyrights, or other intellectual property rights covering subject matter in this document. Except as expressly provided in any written license agreement from R:BASE Technologies, Inc., the furnishing of this document does not give you any license to these patents, trademarks, copyrights, or other intellectual property.

### Trademarks

R:BASE®, Oterro®, RBAAdmin®, R:Scope®, R:Mail®, R:Charts®, R:Spell Checker®, R:Docs®, R:BASE Editor®, R:BASE Plugin Power Pack®, R:Style®, RBZip®, R:Mail Editor®, R:BASE Dependency Viewer®, R:Archive®, R:Chat®, R:PDF Form Filler®, R:FTPClient®, R:SFTPCClient®, R:PDFWorks®, R:Magellan®, R:WEB Reports®, R:WEB Gateway®, R:PDFMerge®, R:PDFSearch®, R:Documenter®, RBInstaller®, RBUpdater®, R:AmazonS3®, R:GAP®, R:Mail Viewer®, R:Capture®, R:Synchronizer®, R:Biometric®, R:CAD Viewer®, R:DXF®, R:Twain2PDF®, R:Scheduler®, R:Scribbler®, R:SmartSig®, R:OutLink®, R:HASH®, R:JobTrack®, R:TimeTrack®, R:Manufacturing®, R:QBDataDirect®, R:QBSynchronizer®, and R:QBDBExtractor®, and Pocket R:BASE® are trademarks or registered trademarks of R:BASE Technologies, Inc. All Rights Reserved. All other brand, product names, company names and logos are trademarks or registered trademarks of their respective companies.

Microsoft MapPoint, Azure Maps, Windows, Windows 11-10, Windows Server 2022-2016, Azure Maps, Word, Excel, Access, SQL Server, and Outlook are registered trademarks of Microsoft Corporation. OpenOffice is a registered trademark of the Apache Software Foundation.

Maptitude is a registered trademark of Caliper Corporation.

Google Maps is a registered trademark of Google, Inc.

MapQuest is a registered trademark of MapQuest, Inc.

Printed: April 2025 in Murrysville, PA

First Edition

## 1.3 License

### R:BASE TECHNOLOGIES, INC. LICENSE AGREEMENT

#### R:Magellan 11 Single Seat License

This is a legal agreement between you, the end user ("**Licensee**"), and R:BASE Technologies, Inc. ("**RBTI**"). Please read the terms and conditions of this License Agreement before using this software. By you selecting "I accept the license agreement" and clicking "Next" during product installation means you expressly accept the terms and conditions of this Agreement. If you do not accept the terms and conditions of this Agreement, you must stop installing the Product and click "Cancel". Your money will be refunded based upon proof of purchase, and in compliance with the return period described in the LIMITED WARRANTY below. A violation of the License, brings damage both financially and to the reputation of RBTI, and in the occurrence of either, both termination of the license agreement and civil damages will be vigorously sought. Once you have clicked "I accept the license agreement", you are entitled to use the Product under the following terms and conditions of this Agreement:

#### LICENSE

This RBTI License Agreement permits you to use one copy of the R:Magellan computer software with associated utilities (the "**Program**") and accompanying user documentation (the "**Documentation**") on any single computer. If you do not have a Site License or at least one 5 Seat Add-On License, this program can only be installed on a single machine. However, you can open multiple sessions and be connected to the same and/or other local or network databases on the same machine simultaneously. (The 5 Seat Add-On License permits additional seats to access the Program, in 5 seat increments if each is physically linked to a single file server and you have obtained a separate license for a Single Seat

version of the Program. 5 Seat Add-On Licenses must be licensed at the same Single Seat version). A Program is "being used" on a computer when it is loaded into a temporary memory or installed on a hard drive in the computer. However, a copy of the Program installed on a network server for the sole purpose of distribution to other computers is not "being used". Each seat having access to the Program must have an appropriate license. If you anticipate that the number of seats with access to the Program will exceed the number of seats for which you are licensed, you must take steps to ensure that the appropriate licenses are obtained for each seat.

#### **5 SEAT ADD-ON AND SITE LICENSES**

If a printed or other form of "hard-copy" License accompanied the copy of the Program you received whose terms vary from this agreement, then the hard-copy License governs your use of the Program. 5 Seat Add-On and Site Licenses allow you to install the Program on the total number of machines for which you are licensed only.

#### **SATELLITE LICENSES**

A Satellite License permits a Licensee to use one copy of the copy of the Program on any additional single computer, for additional development to accompany an existing Single Seat License. The Satellite License must be licensed to the same user as the existing Single Seat License. Each seat having access to the Program must have an appropriate license.

#### **COPYRIGHT AND RESTRICTIONS**

RBTI retains full ownership rights in the Program and Documentation. You may make a single copy of the Program; to be used solely for backup or archival purposes, or you may transfer the Program onto a single hard disk provided you keep the original solely for backup or archival purposes. Such copies shall be owned by RBTI. You may not copy any printed material or Documentation without prior permission. You may not decompile, disassemble cross-compile, reverse engineer, or make or distribute any other form of, or derivative work from, the Program. You may not obscure, alter or remove any RBTI copyright, trademark or proprietary rights notices.

#### **TRANSFER OF LICENSE**

You may not lend, rent or lease the Program or Documentation or any copies to any person. A transfer of license is only authorized through completion of the Consent to Assignment and Assumption of Contract agreement from RBTI. Upon license transfer, you are permanently giving such person possession of all copies of the Program and Documentation, are permanently giving up your right to use the Program and Documentation, and the recipient agrees to the terms of this License Agreement.

#### **STEP UPS AND UPGRADE PURCHASES**

As the Licensee, you are authorized to use the Program only if you are an authorized user of a qualifying product as determined by RBTI. The new license agreement takes the place of the agreement of the qualifying software you stepped up or upgraded from. After you upgrade, you may no longer use the software from which you upgraded. When you install the upgrade, you must uninstall the copy of the qualifying product.

#### **TERM OF LICENSE**

The licensing provided in this License Agreement is perpetual unless you violate any of its terms or conditions, at which time the license will automatically terminate. Upon termination you must return all copies of the Program and Documentation to RBTI or certify in writing to RBTI that all such copies have been destroyed and uninstalled from each workstation and/or network server. RBTI reserves the right to, at its expense and without prior notice, conduct periodic inspections for licensing compliance. If licensee is found to be in violation of current agreement, RBTI may commence a civil action seeking fines, damages, attorney's fees and injunctive relief and may also, in appropriate circumstances, seek criminal prosecution.

#### **ACTIVATION CODES**

The Program requires activation using a unique code. If you purchase a Single Seat License with or without 5 Seat Add-On Licenses, you agree to comply with the license activation and verification procedure described in this section of the Agreement. The activation technology may prevent your use of the Program if you do not follow the activation process described in this Agreement.

Each activation code is tied to one Windows operating system computer. A dual-boot computer with multiple operating systems cannot activate a Single Seat License on more than one operating system. Any software utilities which alter how the Program is installed on a local drive are not supported. This includes any utilities which alter, remove or transfer the location of the Program on the hard drive, or any hard drive utilities which alter the physical properties of the local drive.

The Program activation can be completed automatically through an Internet connection or manually through a provided email option. In doing so, the Program Registration Number and Computer ID must be provided. License validation allows a number of activations based upon the number of licenses purchased.

If a computer is no longer using the Program, through license transfer or hardware failure, the Activation Key that was used on the computer must be submitted to R:BASE Technologies so the key may be disabled, which will then free up that used activation. Once a key is reported as no longer in use and deactivated, it can no longer be used on that computer. Product deactivation can be performed automatically from within R:BASE. To review the License Key and Activation Key product information, select "Help" > "Product Activation" from the Menu Bar.

Licenses for the Corporate VIP Licenses of the Program are not controlled by activation codes and can be operated from computers that are not connected to the Internet.

### **SOFTWARE SUPPORT**

The availability of software support services is subject to the End of Support (EOS) and End of Life (EOL) product life cycle, and to an active Software Assurance Plan. Where applicable, licensees will be provided with an option to upgrade to the current supported version of a software product.

### **LIMITED WARRANTY**

RBTI warrants to you, as the initial user, the Program will perform substantially in accordance with the Documentation, provided it is used in unaltered form with functioning equipment and operating systems for which it was designed. RBTI will, at its option, with proof of payment within 30 days of the invoice date and after the Program with Documentation has been deactivated and uninstalled, and software installer, whether provided by download or other means, permanently deleted from all drives and folders, issue a full refund. These are your sole remedies for any breach of warranty. No exceptions will be made.

### **SERVICES PROVIDED WITH PURCHASE**

#### **1. 30-Day Limited Complimentary Technical Support**

##### **LICENSEE RESPONSIBILITIES**

- To help us expedite the process and provide high quality assistance, the licensee must provide proof of purchase when calling. Proof of purchase is defined as the following: registration number, purchase date, version and build number, and company or individual to which product is registered.
- To have operating system, workstations, and local network installed and functional. RBTI will NOT be responsible for resolving issues not pertaining to the Program.
- Our support staff deals with advanced issues, therefore the person contacting RBTI for assistance should be the system administrator or have other R:BASE/SQL experience and be able to understand and implement the advice given.
- To have the database(s) being converted, safely backed-up before attempting conversion process. RBTI will NOT be held responsible for lost data or corruption as a result of advice given.

##### **R:BASE TECHNOLOGIES, INC. RESPONSIBILITIES**

- To provide quality assistance in a timely manner to aid Licensee in the installation of the product within 30 days of the date of purchase.
- To provide a reasonable solution for any resolvable issue. Not all issues are resolvable, and therefore we will acknowledge the existence of known issues or "bugs" which we are presently aware of, that have no reasonable work-around.

RBTI reserves the right to limit the amount of support time allotted to a maximum of 2 HOURS during the 30-Day Complimentary Technical Support Period. We also reserve the right to limit the quantity of calls from a particular Licensee to 30 MINUTES in a single day. Issues are dealt with on a case-by-case basis, and are handled at the discretion of the support agent assigned to the case. Complimentary Support is limited to INSTALLATION and ELEMENTARY CONVERSION related issues ONLY. Our support hours are from 10am. to 6pm. Eastern Time.

For assistance on your APPLICATIONS, DESIGN, or ADVANCED CONVERSION issues, we offer Technical Support Plans of various types to meet your needs. Please visit the SUPPORT area of our website at [www.rbase.com](http://www.rbase.com) for details and pricing.

## **2. Fixes for Known Issues**

RBTI will provide continued product fixes for known issues or "bugs" for 1 YEAR from the software purchase date. After 1 year, users are urged to acquire the necessary Software Assurance Plan to continue with product support and ongoing activations for reinstallations and license transfers.

## **3. Enhancement Requests**

RBTI will provide continued product enhancements for requested features for 1 YEAR from the software purchase date. After 1 year, users are urged to acquire the necessary Software Assurance Plan to continue with product support and ongoing activations for reinstallations and license transfers.

## **4. Periodic Activations**

RBTI will provide periodic product activations of license transfers and/or reinstallations for 1 YEAR from the R:BASE purchase date. Any activation requests that occur beyond the 1 Year purchase date will require an active Software Assurance Plan.

## **NO OTHER WARRANTIES**

Except as explicitly stated above, RBTI makes no express or implied warranties (including any warranties of merchantability or fitness) with respect to the character, function, or capabilities of the program, the documentation or their appropriateness for any user's purposes. RBTI cannot customize product(s) to meet specific needs in all cases. Examples of customization include, but are not limited to: special character sets, foreign language adaptations, specific device drivers or other localization issues. Under no circumstances will RBTI be held responsible for product functionality once alterations have been made to accommodate individual needs.

## **DISCLAIMER OF WARRANTY**

The Program and the accompanying files are sold "as is" and without warranties as to performance or merchantability or any other warranties whether expressed or implied. Because of the various hardware and software environments into which the Program may be put, No warranty of fitness for a particular purpose is offered. Good data processing procedure dictates that any program be thoroughly tested with non-critical data before relying on it. The user must assume the entire risk of using the Program. Any liability of the seller will be limited exclusively to product replacement or refund of purchase price.

## **HIGH RISK ACTIVITIES**

The Program is not fault-tolerant and is not designed, manufactured or intended for use or resale as on-line control equipment in hazardous environments requiring fail-safe performance, such as in the operation of nuclear facilities, air traffic control, aircraft navigation or communication systems, direct life support machines, or weapons systems, in which the failure of the Program could lead directly to death, personal injury, or severe physical or environmental damage ("High Risk Activities"). RBTI specifically disclaims any expression or implied warranty of fitness for High Risk Activities.

## **LIMITATIONS ON LIABILITIES**

RBTI will not be responsible for any costs or damages associated with loss of the use of the Program or any other resources, loss of business or profits, any loss of data, any third-party claims or costs of substitute programs. In no event will RBTI be liable for any incidental, indirect, special, consequential or punitive damages suffered by the user or any other person or entity, whether from the use of the program or documentation, any failure thereof, or otherwise, even if RBTI or its dealers or agents are aware of the possibility of such damages. In no event will RBTI aggregate liability to you or anyone else exceed two times the license fee you paid for the program and documentation in this package. Because some states do not allow the limitation or exclusion of implied warranties and liabilities for consequential or incidental damages, the above limitations may not apply to you.

## **GENERAL**

This License Agreement constitutes the full and complete agreement between parties. RBTI retains all rights not specifically granted herein. RBTI shall not be deemed to have waived any of its rights hereunder or under all copyright laws, trade secrecy laws or otherwise. This Agreement is intended as a legally binding agreement which will be enforced to the full extent permitted under applicable law, in whole or in part. If any one provision of this Agreement is declared invalid or unenforceable, all remaining provisions shall never less remain in effect. The laws of the state of Pennsylvania shall govern this Agreement. RBTI reserves the right to amend, alter, or revoke this agreement at any time. All revisions to this license agreement are available for inspection upon request, supersede conditions in all

past agreements, and render prior license agreements void and unenforceable. Both parties named in this license will only be bound to the terms of the most current revision of this agreement.

**U.S. GOVERNMENT RESTRICTED RIGHTS**

Use, duplication or disclosure by the Government, its agents or employees is subject to all restrictions imposed by law, regulation or government directive, including but not limited to those restrictions set forth in DFARS 252.227-7013 and 48CFR 52.227-19, as applicable.

R:BASE Technologies, Inc.  
<https://www.rbase.com>  
[rbaseinfo@rbase.com](mailto:rbaseinfo@rbase.com)

Copyright 1982-2025 R:BASE Technologies, Inc.  
All Rights Reserved  
Revised Monday, April 28, 2025

## 1.4 Complimentary Support

### 30 DAY LIMITED COMPLIMENTARY TECHNICAL SUPPORT

#### A. LICENSEE RESPONSIBILITIES.

1. To help us expedite the process and provide high quality assistance, the licensee must provide proof of purchase. Proof of purchase is defined as the following: registration number, purchase date, version and build number, and company or individual to which product is registered.
2. To have operating system, workstations, and local network installed and functional. R:BASE Technologies will NOT be responsible for resolving issues not pertaining to the software product.
3. Our support staff deals with advanced issues, therefore the person contacting R:BASE Technologies for assistance should be the system administrator or have other R:BASE/SQL experience and be able to understand and implement the advice given.
4. To have the database, application, and command files being reviewed, safely backed-up before attempting assistance. R:BASE Technologies will NOT be held responsible for lost data or corruption as a result of advice given.


#### B. R:BASE TECHNOLOGIES, INC. RESPONSIBILITIES.

1. To provide quality assistance in a timely manner to aid in the installation of the product and elementary conversion of database, application, and command files within 30 days of the date of purchase.
2. To provide a reasonable solution for any solvable issue. Not all issues may be solved, and therefore we will acknowledge the existence of known issues, or bugs, which we are presently aware of, that have no reasonable work-around.

R:BASE Technologies reserves the right to limit the amount of support time allotted to a maximum of 2 HOURS during the 30-Day Complimentary Technical Support period. We also reserve the right to limit the quantity of calls from a particular licensee to 30 MINUTES in a single day. Issues are dealt with on a case-by-case basis, and are handled at the discretion of the support agent assigned to the case. Complimentary Support is limited to INSTALLATION and ELEMENTARY CONVERSION related issues ONLY. Our support hours are Monday through Friday, from 10:00 AM to 6:00 PM (EST).

For application, design, or advanced conversion assistance, R:BASE Technologies offers Technical Support Plans of various types to meet your needs. Please visit the Support page at <https://www.rbase.com/support> for details and pricing.

**Part**





## 2 Installation

### 2.1 System Requirements

The following system specifications are recommended for the optimal use of R:BASE and R:BASE-related software.

#### Workstation Hardware

- 2-Core 2GHz+ CPU
- 2 GB of available RAM (4 GB recommended)
- 2 GB of available hard disk space
- 1024x768 or higher resolution video adapter and display
- Standard mouse or compatible pointing device
- Standard keyboard

#### Server Hardware

- 2-Core 2GHz+ CPU
- 6 GB of available RAM (8 GB recommended)

#### Operating System

- Microsoft Windows 11 (Professional)
- Microsoft Windows 10 (Professional)
- Microsoft Windows Server 2025
- Microsoft Windows Server 2022
- Microsoft Windows Server 2019
- Microsoft Windows Server 2016

#### Network

- Ethernet infrastructure (Gigabyte recommended)
- Internet connection recommended, but not required, for license activation, software updates, and support
- Anti-virus programs should exclude the R:BASE program, and any add-on product, executable and database files

### 2.2 Things You Will Need

- License Key

Before launching the installer, it is recommended that you have your 32-character License Key readily available. The License Key is provided in a document, with the email message, when the software was originally purchased. If you have lost or misplaced your License Key, please contact our Support Staff by email at [support@rbase.com](mailto:support@rbase.com).

- Internet Access

The computer where the software will be launched should have access to the Internet for activation. The Internet access is used to visit the R:BASE Technologies Web site to provide your required Activation Key.

In instances where the software will be installed on a computer that is not connected to the Internet, you must then contact R:BASE Technologies to provide information displayed on the computer screen. Please contact our Product Activation Staff by email at [activationkey@rbase.com](mailto:activationkey@rbase.com). The Registration Number must be provided. The Registration Number is displayed on the invoice/order slip, and within the email, when the software was originally purchased.

## 2.3 Software Installation

The installation of R:Magellan is fully automated, and does not require user intervention for the initial configuration.

Run the installer ".exe", provided by download, while physically sitting at the workstation to begin the installation process, and read the installer screens for licensing and other information as the program installs.

### Installation Directory

C:\RBTI\RMagellan11

### Files Installed

RMagellan11.rbm  
libeay32.dll  
ssleay32.dll  
RMagellan11.chm  
RMagellan11.pdf  
RMagellan11.ico  
License.rtf  
ReadMe.txt

### Requirements

1. The R:Magellan 11 plugin file (RMagellan11.rbm) must be placed in the R:BASE 11 program directory (default: C:\RBTI\RBG11) or the runtime/compiled application directory. The SSL DLLs (libeay32.dll, ssleay32.dll) must also be placed in the folder if Google Maps will be specified as the [map engine](#).
2. To display maps with driving instructions, R:Magellan uses MS Edge as the embedded browser, where the [WebView2 Runtime](#) must be downloaded and installed. WebView2 Runtime is an Edge installation that is designed for embedding the engine in third party applications (R:BASE/R:Magellan). It recommended to download the Evergreen Standalone Installer (x86 installer). If you have Windows 11 (or higher) or MS Office installed, the WebView2 Runtime is likely already loaded. To check if WebView2 Runtime is installed, use the CHECK\_WEBVIEW2 parameter with the GETPROPERTY command (below) at the R> Prompt. The "vWebView2Install" variable value will be either "OK" or "NOT FOUND".

```
GETPROPERTY APPLICATION CHECK_WEBVIEW2 'vWebView2Install'  
SHOW VAR vWebView2Install
```

3. The WebView2Loader.dll file must be located in the R:BASE program folder. For R:Compiler/Runtime for R:BASE use, the WebView2Loader.dll must be copied from the R:Compiler/Runtime for R:BASE program folder to the compiled/runtime application folder.

## 2.4 Plugin Activation

R:BASE Plugins can be used to enhance, or extend R:BASE operations. Current R:BASE Plugins use the .RBM file extension.


To begin using any plugin product, the plugin must be registered for use.

The license type for R:BASE and R:BASE plugin products must match. The license keys supplied with Single Seat and 5 Seat plugin products will only be accepted within Single Seat and 5 Seat versions of R:BASE, and are not accepted within R:Compiler for R:BASE or Runtime for R:BASE programs. The same license structure is also in place for Runtime License Keys for plugin products, where the key will not be accepted within Single Seat and 5 Seat Licenses R:BASE.


## 2.4.1 R:BASE

To begin using a plugin product, you must register the software within R:BASE by selecting "Help" > "Product Activation" from the main Menu Bar. In this window, select the "Add New" button where you can enter or copy and paste the License Key you received with your product.


Only "Per Seat" License Keys are valid for this entry screen. All "Runtime" License Keys must be registered within R:Compiler for R:BASE or within Runtime for R:BASE separately.

A dialog box titled "License Information" with a close button (X) in the top right corner. It contains a label "Enter License Key:" followed by a text input field divided into eight segments by hyphens. Below the input field are three buttons: "Paste" with a clipboard icon, "OK" with a green checkmark icon, and "Cancel" with a red X icon.


After entering the License Key, you will see a dialog to prompt for your activation method. The software can be activated automatically over the Internet, or manually by retrieving an Activation Key from R:BASE Technologies by email or over the phone. If you select "Later", you will be reminded each time R:BASE starts to activate your copy.

A dialog box titled "R:BASE Activation Wizard" with a close button (X) in the top right corner. It contains the text "Select activation method:" followed by three radio button options. The first option, "Automatic activation process (recommended)", is selected and includes the text: "It is the easiest and quickest way to activate your software. Make sure your Internet connection is established. The wizard will automatically activate the product." The second option is "Manual activation process" with the text: "Use this option if the automatic activation failed for any reason, or if you prefer to send an e-mail to obtain an Activation Key." The third option is "Activate later". At the bottom are three buttons: "< Back", "Next >", and "Cancel".

When activating the software manually, you select the e-mail link to launch your email client and send a pre-formatted message to R:BASE Technologies that will contain your License Key and the displayed Computer ID. You will need to provide your R:BASE Registration Number and Computer ID.



At any time, you can review your product information by starting R:BASE, and from the Menu Bar clicking on "Help" > "Product Activation". Your R:BASE Registration Number is displayed on the window. You can also enter additional License Keys for R:BASE add-on products.




**Please be advised that if you are activating multiple workstations, it is highly recommended that you keep records of the computer name, Computer ID and Activation Key for future reference. Access to this information will prove convenient in the event of a hardware failure or license transfer when uninstalling R:BASE.**

**Please see:** [Uninstall/Reinstall](#)

## 2.4.2 R:Compiler for R:BASE

### Runtime License Key

Runtime license keys for an R:BASE Plugin must be stored within the compiled executable. A specific Runtime License Key would be provided after your purchase of the Runtime software product. Adding a Runtime License to your project can be done by selecting the "Add License" button, and pasting the appropriate Runtime License Key into the displayed dialog window.



After a Runtime License is added as a resource, it will be assigned a "Resource ID". This ID consists of the word "License" and an incrementing value for the number of licenses added to the executable.

### Plugin File (.RBM)

R:BASE Plugin files can be added and stored within the compiled executable or included within the R:BASE application directory. The Runtime license key pertaining to the R:BASE Plugin must be stored in the compiled executable.

Adding a Plugin to the list of resources can be performed by selecting the "Add Plugin" button on the Tool Bar. You will be prompted to locate the appropriate Plugin file with the .RBM file extension. After a Plugin file is added as a resource, it will be assigned a "Resource ID". This ID consists of the Plugin file name.

## 2.4.3 Runtime for R:BASE


After R:BASE Plugins are acquired for Runtime for R:BASE applications, the Plugin file must be included in the Runtime application folder, to be loaded when the Runtime application launches.

To load the Plugin, the License Key must be included into the Runtime for R:BASE session by adding the following PROPERTY command within the application startup file:

```
PROPERTY ADD_LICENSE #####-#####-#####-#####-#####-#####-#####-##### ' '
```

# Part


---



### 3 Uninstall


If a computer is no longer using R:Magellan, through license transfer or hardware failure, the Activation Key that was used on that computer must be submitted to R:BASE Technologies so we can then remove the Activation Key from our log. We will disable the Key, which will then free up that used activation. Once a key is reported to us as no longer in use and deactivated, it can no longer be used on that computer.

Product deactivation can be performed automatically from within R:BASE. To review your product information select "Help" > "Product Activation" from the Menu Bar. Here, the License Key and Activation Key for a selected product is available for review.



If the License Key for your product is not readily available for the license transfer, select the "Copy License Key" button to send your License Key to the clipboard.

To deactivate a listed product, select it and press the "Deactivate" button. The below confirmation dialog will appear. After selecting "Yes", the product will be removed from the list.



After completing the deactivation of the product, it can be successfully reinstalled and activated.

**Part**

**IV**



## 4 Map Engine Comparison

R:Magellan is a R:BASE Technologies Plugin product for integrating powerful mapping and analysis features into R:BASE applications. R:Magellan offers several map engine solutions, including MapPoint and Maptitude as software programs, as well as HERE Maps, Google Maps, Azure Maps, and MapQuest as online services. Each provides fast geographical travel instructions for multiple locations.

The following map engine comparison details the differences between each:

Feature	MapPoint	Maptitude	Here Maps	Azure Maps	Google Maps	MapQuest
Map Engine Type	Software	Software	Online	Online	Online	Online
License	Installation	Installation	Pay for Service	Pay for Premium Service	Pay for Premium Service	Pay for Premium Service
Query Limit	None	None	Plan Based	Plan Based	Plan Based	Plan Based
Waypoint (Address)	Yes	Yes	Yes	Yes	Yes	Yes
Coordinates	Yes	Yes	Yes	Yes	Yes	Yes
Route Calculation	Yes	Yes	Yes	Yes	Yes	Yes
Address Checking	Yes	No	No	Yes	Yes	No
Map Display	Yes	Yes	Yes	Yes	Yes	No
Driving Cost Units	Yes	No	No	No	No	No
Driving Cost	Yes	No	No	No	No	No
Optimization	Yes	Yes	Yes	Yes	Yes	Yes
Show Progress	Yes	Yes	Yes	Yes	Yes	Yes
Symbols	Yes	Yes (pin)	No	No	No	No
Map Styles	Yes	Yes	No	No	No	No
Save/Load Maps	Yes	Yes	No	No	No	No
Map Legend	Yes	Yes	No	No	No	No
Window State	Yes	Yes	Yes	Yes	Yes	Yes
Print Maps	Yes	Yes	No	No	No	No
Direction File	Yes	Yes	Yes	Yes	Yes	Yes
Miles/Kilometers Values	Yes	Yes	Yes	Yes	Yes	Yes
Coordinates for Stops	Yes	Yes	Yes	Yes	Yes	Yes
Total Trip Distance	Yes	Yes	Yes	Yes	Yes	Yes
Total Trip Duration	Yes	Yes	Yes	Yes	Yes	Yes
Number Stops in Route	Yes	Yes	Yes	Yes	Yes	Yes

Microsoft MapPoint and Azure Maps are registered trademarks of Microsoft Corporation.

Maptitude is a registered trademark of Caliper Corporation.

Here Maps is a registered trademark of HERE Global B.V.

Google Maps is a registered trademark of Google, Inc.

MapQuest is a registered trademark of MapQuest, Inc.

**Part**

**V**

## 5 Working With MapPoint

The following details the specific use of R:Magellan with Microsoft MapPoint.

### Syntax:

```
PLUGIN RMagellan 'VarName|<Parameter Value>'
```

### Where:

"**VarName**" is the resulting text variable which returns the status, such as 'OK' or the exact -ERROR- message.

"**Parameter**" is the available option recognized by the Plugin.

"**Value**" is the specific value used by the available parameter.

### Notes:

- The R:Magellan parameters can be any number of values, but a starting location and ending location must be specified in order for a mapped route to be provided. Each address parameter must be separated with the pipe "|" character.
- MapPoint must be installed and configured accordingly on your workstation in order to use the program with R:Magellan.
- The R:Magellan Plugin returns variable values based upon the configuration settings within your MapPoint software. Be sure to review your route settings within MapPoint. Available options include:
  - Average driving day
  - Automatic rest stops
  - Driving speeds
  - Fuel consumption
  - Driving costs
  - Units (miles, kilometers)
- In the event an address has multiple hits or is invalid, the MapPoint "Find" dialog will be displayed to specify a different address, and then select the "Find" button.

**Find**

Address Place / Data Lat/Long

Country:  
United States

Type as much of the address as you can.

Street address:  
603 N St SW

City:  
Quincy

State: WA-Washington ZIP code: 98448

The Terr, Lakewood Center, WA 98499  
The Plaza, Vancouver, WA 98664  
98448 (postal code), Washington, United St...  
Quincy, Washington, United States

OK Cancel

## 5.1 Map Calculation

The Map Calculation parameters control how a map route is calculated.

Parameters	Values (bold values are default)	Description
ROUTE_CALCULATION	<b>ON</b> OFF	Specifies whether the route is calculated
DRIVING_COST_UNITS	0 1 2 3	Returns or sets the method used to determine route costs.  0 = Cost based on fixed rate per GeoUnit (mile/kilometer) 1 = Cost based on price per liter of fuel 2 = Cost based on price per U.S. gallon of fuel 3 = Cost based on price per U.K. gallon of fuel
DRIVING_COST	Currency	Returns or sets the fuel price or fixed cost for determining route costs, depending on the method set in the <b>DRIVING_COST_UNITS</b> property.
DEGREES	<b>ON</b> OFF	Specifies if Latitude/Longitude return variables will be returned as a <b>DOUBLE</b> data type values ( <b>OFF</b> ).
OPTIMIZATION	ON <b>OFF</b>	Specifies whether optimization is used. With optimization set <b>ON</b> , you can reorder the intermediate stops on your route so that your travel time between the start and end points is the most time-efficient.
SHOW_PROGRESS	ON <b>OFF</b>	Specifies whether a progress window is displayed while calculations are processing.


Waypoint Address	Text	The waypoint address can be defined as a valid street address or by Latitude and Longitude coordinates.
------------------	------	---

	<p>When assigning a route, the waypoint addresses should be listed from start to finish in the order of arrival. The starting and ending points, would be listed first and last. Or, you could use the OPTIMIZATION parameter above.</p> <p>The street address value must contain a street number and name followed by a comma, then the city followed by another comma, and then the state and zip code. A correct address parameter example for R:BASE Technologies, Inc. is:</p> <p style="text-align: center;">3935 Old William Penn Highway, Murrysville, PA 15668</p> <p>The above street address format is specific to the United States. In other countries, the address format will vary. For example, the address format for a waypoint address in Sweden would begin with the street name and street number followed by a comma, then the zip code, followed by another comma, and then the city:</p> <p style="text-align: center;">Hästholsvägen 32, 131 30, NACKA</p> <p>The waypoint address can also be defined as Latitude and Longitude coordinates. The coordinates must be defined in the decimal format, but as the TEXT data type. The accuracy of your location depends on the number of decimal values. Two different formats are supported to pass a location to R:Magellan. Two correct Latitude and Longitude coordinates parameter examples would be:</p> <p style="text-align: center;">COORDINATES 24.54410 ° NORTH~81.80530 ° WEST COORDINATES 24.54410~-81.80530</p> <p>Additional options are available as to how your waypoint Address is displayed on the map allowing you to edit the address caption, symbol, and bubble itself. These additional option with the pound "#" character must be defined in the order below.</p> <p>#CAPTION value# - will alter the main caption of the bubble</p> <p>#SYMBOL value# - will change the symbol icon for the waypoint address. A list of 255 available symbols, by number are provided below.</p> <p>#DISPLAY value# - will define how the bubble is displayed. The three available options for DISPLAY are:</p> <ul style="list-style-type: none"> <li>• BALLOON</li> <li>• NAME</li> <li>• NONE</li> </ul> <p>These additional options are included with the waypoint address parameter and must be positioned within the pipe symbols in your command syntax. Additional options added the examples above are:</p> <p style="text-align: center;">#CAPTION RBTI##SYMBOL 81#3935 Old William Penn Highway, Murrysville, PA 15668</p> <p style="text-align: center;">#CAPTION RBTI##DISPLAY NAME#COORDINATES 40.4284 ° NORTH~79.6958 ° WEST</p> <p style="text-align: center;">#CAPTION RBTI##DISPLAY NAME#COORDINATES 40.4284~-79.6958</p>
--	---

### Symbols

There are different sets of symbols available based upon the version of MapPoint that is used with R:Magellan.


Symbols in MapPoint 2010-2013:



208	209	210	211	212	213	214	215
216	217	218	219	220	221	222	223
224	225	226	227	228	229	230	231
232	233	234	235	236	237	238	239
240	241	242	243	244	245	246	247
248	249	250	251	252	253	254	255
256	257	258	259	260	261	262	263
264	265	266	267	268	269	270	271
272	273	274	275	276	277	278	279
280	281	282	283	284	285	286	287
288	289	290	291	292	293	294	295
296	297	298	299	300	301	302	303

304	305	306	307	308	309	310	311
312	313	314	315	316	317	318	319
320	321	322	323	324	325	326	327
328	329	330	331	332	333	334	335
336	337	338	339	340	341	342	343
344	345	346	347				

Symbols in MapPoint 2009:





Symbols in MapPoint 2006 and below:



## 5.2 Map Display

The Map Display parameters control how a map route is displayed.

Parameters	Values (bold values are default)	Description
LOAD_MAP	filename	Loads a saved map from a file
SAVE_MAP	filename	Saves the current map, with waypoints, and all other objects to file
SHOW_MAP	<b>ON</b> OFF	Specifies whether the map will be displayed
MAP_STYLE	<b>DATA</b> POLITICAL ROAD ROAD_DATA	Specifies the map style

	TERRAIN	
ITINERARY_VISIBLE	<b>ON</b> OFF	Specifies whether the route itinerary is visible
TOOLBARS	<b>ON</b> OFF	Specifies whether the MapPoint toolbars are displayed when a map is launched
PANE_STATE	LEGEND NEARBY_PLACES <b>ROUTE_PLANNER</b> NONE	Specifies the window pane displayed on the left side of the map and directions
WINDOW_STATE	MINIMIZED <b>MAXIMIZED</b> NORMAL	Specifies the R:Magellan window state when the map is displayed
FORM_CAPTION	value	Specifies text to appear in the form caption after "R:Magellan"

## 5.3 Printing Maps

The Printing Maps parameters control how a map route is printed. A map can be printed while you are viewing the map as well as through the command syntax parameters.

When you are viewing the map in the R:Magellan window, right-click anywhere in the directions panel, select "Edit" or "Open" and click on the "Print" icon to print different selected information. The following Print options are available:

- Select appropriate printer
- Print to file
- Print Current Map View
- Print Driving Directions Only
- Print Turn-by-Turn Maps
- Strip Maps
- Selected Map Area
- Highlighted Places Maps
  - Include Overview Map
- Number of Copies
- Title (Optional)
- Map Quality (Draft, Normal, Presentation)
  - Print Faxable Map
- More Options:
  - Print Route in as few pages as possible
  - Print high-detail strip maps using more pages
  - Print each stop on a separate page
  - Print each day on a separate page
  - Print a new page every [nnnn] miles
  - Print a new page every [nn] hours
  - Include Summary Statistics
  - Automatically Select Page Orientation

### Print Parameters

Parameters	Values (bold values are default)	Description
PRINT_MAP	<b>ON</b> <b>OFF</b>	Specifies whether the map will be printed
PRINT_TITLE	text value	Specifies the text title
PRINT_COPIES	integer value	Specifies the number of copies
INCLUDE_OVERVIEW	<b>ON</b> <b>OFF</b>	Indicates whether the Overview Map is included in the printout.
INCLUDE_LEGEND	<b>ON</b> <b>OFF</b>	Indicates whether the map legend is included in the printout.

PRINT_AREA	<b>MAP</b>	<b>MAP</b> - prints the area of the map currently displayed on the screen
	DIRECTIONS	<b>DIRECTIONS</b> - prints the driving directions as text in Portrait mode; no maps are printed
	TURN_BY_TURN	<b>TURN_BY_TURN</b> - prints turn-by-turn maps in Portrait mode; miniature maps showing the intersections of every turn along the route
	STRIP_MAPS	<b>STRIP_MAPS</b> - prints strip maps in Landscape mode, one page per route segment, with a strip map displayed on the left side of each page and the corresponding driving directions on the right
	SELECTED_AREA	<b>SELECTED_AREA</b> - prints only the selected area of the map
	HIGHLIGHTED_PLACES	<b>HIGHLIGHTED_PLACES</b> - prints a street-level map for each highlighted place and Pushpin, along with any associated Pushpin text
	FULL_PAGE	<b>FULL_PAGE</b> - prints extended maps to use a full page
PRINT_QUALITY	<b>NORMAL</b> <b>DRAFT</b> <b>PRESENTATION</b>	Specifies the resolution. DRAFT is low quality and PRESENTATION is high quality.
PRINT_ORIENTATION	<b>PORTRAIT</b> <b>LANDSCAPE</b> <b>AUTO</b>	Specifies whether a map prints vertically, horizontally, or automatically on a page
COLLATE	<b>ON</b> <b>OFF</b>	Specifies whether multiple copies will print in pre-sorted order
FAXABLE	<b>ON</b> <b>OFF</b>	Indicates whether to print a black and white map that is suitable for faxing. If ON, the printed map is faxable. Default value is OFF.

## 5.4 Return Variables

After the Plugin is launched, return variables are calculated for the total distance, trip duration, driving time, an estimated trip cost, longitude and latitude for each address, the distance traveled between the addresses, and the number of addresses provided. The first address listed is the origin. Each following address provided will be listed a destination on the map, incrementing by 1. A latitude and longitude variable is generated for each address given.

A distance variable is generated from the origin to the first destination. For each additional address provided, a distance variable is generated between those destinations. An elapsed distance is also provided from the origin to each destination on the route. The number of variables returned depend on the number of address parameters you insert into the PLUGIN command.

Variable Name	Data Type	Description
vDrivingDistance	DOUBLE	Total trip distance in miles
vTripDuration	INTEGER	Total trip duration in minutes (driving and not driving)
vDrivingTime	INTEGER	Total driving time in minutes
vTripCost	CURRENCY	Total estimated trip cost
vOriginLat	TEXT	Latitude coordinate for the origin
vOriginLong	TEXT	Longitude coordinate for origin
vOriginAddress	TEXT	Address for origin
vDest1Lat	TEXT	Latitude coordinate for first destination
vDest1Long	TEXT	Longitude coordinate for first destination
vDest1Addr	TEXT	Address for first destination
vDest2Lat	TEXT	Latitude coordinate for second destination
vDest2Long	TEXT	Longitude coordinate for second destination
vDest2Addr	TEXT	Address for second destination

vDest1Dist	DOUBLE	Distance in miles from origin to first destination
vDest2Dist	DOUBLE	Distance in miles from first destination to second
vDest1Elapsed	DOUBLE	Distance in miles from origin to first destination
vDest2Elapsed	DOUBLE	Distance in miles from origin to second destination
vDestCount	INTEGER	Number of addresses in map route

## 5.5 Examples

### 5.5.1 Example 1

-- To launch a mapped route from the prior Microrim headquarters to the  
 -- prior R:BASE Technologies, Inc. headquarters and save the map to a file

```
SET VAR vStartAddress TEXT = +
'#CAPTION MICRORIM##SYMBOL 74#15395 SE 30th Place, Bellevue, WA 98007'


SET VAR vEndAddress TEXT = +
'#CAPTION RBTi##SYMBOL 75#3935 Old William Penn Highway, Murrysville, PA
15668'

SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|SHOW_MAP ON +
|PANE_STATE NONE +
|TOOLBARS ON +
|WINDOW_STATE NORMAL +
|ROUTE_CALCULATION ON +
|ITINERARY_VISIBLE OFF +
|DRIVING_COST_UNITS 1 +
|DRIVING_COST $3.15 +
|MAP_STYLE ROAD|' + .vStartAddress + '|' + .vEndAddress)
&vPlugin
CLEAR VAR vPlugin, vStartAddress, vEndAddress
RETURN
```

--the following variables are returned

vDrivingDistance	= 2540.4	DOUBLE
vTripDuration	= 6220	INTEGER
vDrivingTime	= 2380	INTEGER
vTripCost	= \$709.80	CURRENCY
vOriginLat	= 47.582494° North	TEXT
vOriginLong	= 122.13518° West	TEXT
vDest1Lat	= 40.428355° North	TEXT
vDest1Long	= 79.695849° West	TEXT
vDest1Elapsed	= 2540.4	DOUBLE
vDest1Dist	= 2540.4	DOUBLE
vDestCount	= 2	INTEGER

The following map is launched:



## 5.5.2 Example 2

- To launch a mapped route from the western most point in the
- United States (contiguous) to the Alamo in Texas, to the steps
- of the U.S. Supreme Court, to the southern most point of the
- United States (contiguous)

```
SET VAR vStartAddress TEXT = +
'#CAPTION Western Most Point##SYMBOL 92##DISPLAY NAME#COORDINATES 48.16350
° NORTH~124.7310 ° WEST'
```

```
SET VAR vSecondAddress TEXT = +
'#CAPTION The Alamo##SYMBOL 78##DISPLAY NAME#300 Alamo Plaza, San Antonio,
Texas 78205'
```

```
SET VAR vThirdAddress TEXT = +
'#CAPTION US Supreme Court##SYMBOL 117##DISPLAY NAME#131 1st Street,
Washington, DC 20002'
```

```
SET VAR vEndAddress TEXT = +
'#CAPTION Southern Most Point##SYMBOL 108##DISPLAY NAME#COORDINATES
24.5441~-81.8053'
```

```
SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|SHOW_MAP ON +
```

```

|PANE_STATE NONE +
|TOOLBARS ON +
|WINDOW_STATE NORMAL +
|ROUTE_CALCULATION ON +
|ITINERARY_VISIBLE ON +
|DRIVING_COST_UNITS 1 +
|DRIVING_COST $3.15 +
|MAP_STYLE ROAD|' + +
.vStartAddress + '|' + .vSecondAddress + '|' + .vThirdAddress + '|' +
.vEndAddress)
&vPlugin
CLEAR VAR vPlugin, vStartAddress, vSecondAddress, vThirdAddress,
vEndAddress
RETURN


```

--the following variables are returned

vDrivingDistance	= 5263.	DOUBLE
vTripDuration	= 14812	INTEGER
vDrivingTime	= 5194	INTEGER
vTripCost	= \$1,492.31	CURRENCY
vOriginLat	= 48.163509° North	TEXT
vOriginLong	= 124.731008° West	TEXT
vDest1Lat	= 29.425189° North	TEXT
vDest1Long	= 98.486464° West	TEXT
vDest2Lat	= 38.891344° North	TEXT
vDest2Long	= 77.005844° West	TEXT
vDest3Lat	= 24.544106° North	TEXT
vDest3Long	= 81.805297° West	TEXT
vDest1Elapsed	= 2431.	DOUBLE
vDest1Dist	= 2431.	DOUBLE
vDest2Elapsed	= 4036.2	DOUBLE
vDest2Dist	= 1605.2	DOUBLE
vDest3Elapsed	= 5263.	DOUBLE
vDest3Dist	= 1226.8	DOUBLE
vDestCount	= 4	INTEGER

The following map is launched:





### 5.5.3 Example 3

- To launch a mapped route from the Pittsburgh International Airport
- to the R:BASE Conference

```
SET VAR vStartAddress TEXT = +
'#CAPTION PGH Airport##SYMBOL 90##DISPLAY NAME#COORDINATES 40.49620~-
80.25425'

SET VAR vEndAddress TEXT = +
'#CAPTION R:BASE Conference##SYMBOL 200##DISPLAY NAME#3962 William Penn
Highway, Monroeville, PA 15146'

SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|SHOW_MAP ON +
|PANE_STATE NONE +
|TOOLBARS ON +
|WINDOW_STATE NORMAL +
|ROUTE_CALCULATION ON +
|ITINERARY_VISIBLE ON +
|DRIVING_COST_UNITS 1 +
|DRIVING_COST $3.15 +
|MAP_STYLE ROAD +
|INCLUDE_OVERVIEW ON +
```

```


| INCLUDE_LEGEND ON +
| PRINT_AREA TURN_BY_TURN +
| PRINT_TITLE Printing MAP Using R:Magellan! +
| PRINT_ORIENTATION LANDSCAPE|' + .vStartAddress + '|' + .vEndAddress)
&vPlugin
RETURN

```

--the following variables are returned

vDrivingDistance	= 31.1	DOUBLE
vTripDuration	= 42	INTEGER
vDrivingTime	= 42	INTEGER
vTripCost	= \$11.09	CURRENCY
vOriginLat	= 40.496204° North	TEXT
vOriginLong	= 80.254246° West	TEXT
vDest1Lat	= 40.431077° North	TEXT
vDest1Long	= 79.792183° West	TEXT
vDest1Elapsed	= 31.1	DOUBLE
vDest1Dist	= 31.1	DOUBLE
vDestCount	= 2	INTEGER

The following map is launched:





### 5.5.4 Example 4

-- To create a mapped route from the Pittsburgh International Airport  
-- to the R:BASE Conference, and then saved the route to a map file

```
SET VAR vStartAddress TEXT = +  
'#CAPTION PGH Airport##SYMBOL 90##DISPLAY NAME#COORDINATES 40.49620~-  
80.25425'  
  
SET VAR vEndAddress TEXT = +  
'#CAPTION R:BASE Conference##SYMBOL 200##DISPLAY NAME#3962 William Penn  
Highway, Monroeville, PA 15146'  
  
SET VAR vPlugin TEXT = +  
( 'PLUGIN RMagellan vResult +  
|ROUTE_CALCULATION ON +  
|DRIVING_COST_UNITS 1 +  
|DRIVING_COST $3.15 +  
|MAP_STYLE ROAD +  
|SHOW_MAP OFF +  
|SAVE_MAP C:\RBTI\Conference.ptm|' + .vStartAddress + '|' + .vEndAddress )  
&vPlugin  
CLEAR VAR vPlugin, vStartAddress, vEndAddress  
RETURN
```

### 5.5.5 Example 5

-- To load a map file

```
PLUGIN RMagellan vResult +  
|LOAD_MAP C:\RBTI\RBTI.ptm +  
|SHOW_MAP ON
```

**Part**

**VI**

## 6 Working With Azure Maps

The following details the specific use of R:Magellan with Azure Maps.

### Syntax:

```
PLUGIN RMagellan 'VarName|<Parameter Value>'
```

### Where:


"**VarName**" is the resulting text variable which returns the status, such as 'OK' or the exact -ERROR- message.

"**Parameter**" is the available option recognized by the Plugin.

"**Value**" is the specific value used by the available parameter.

### Notes:

- The R:Magellan parameters can be any number of values, but a starting location and ending location must be specified in order for a mapped route to be provided. Each address parameter must be separated with the pipe "|" character.
- An Azure Maps API key must be acquired and included with the PLUGIN syntax in order to use Azure's map and direction services with R:Magellan. See "Accessing Azure Maps Services" below.
- In the event an address or coordinates has multiple hits or is invalid, the "Find Address" dialog will be displayed to specify a different address. The "Address" field and "Find" button can be used to perform multiple searches for repeated search inquiries, where the user can enhance the address field contents to pinpoint the desired destination. Once a desired address is located and highlighted, the "Use Address" button is selected to use that destination.



### Accessing Azure Maps Services

1. Sign in to the Azure portal. <https://portal.azure.com/>
2. Select to "Create a resource"
3. Search for and select Maps, then click Create within the "Azure Maps" panel.
4. You will be redirected to the subscription screen if you do not have a subscription. If you have a subscription, you can create an Azure Maps Account resource.
5. Enter your new account's required information and click the "Review + create" button.
6. Once the creation is complete, select All resources in the Azure services section, then select your Azure Maps account.
7. Open your created Azure Maps account and navigate to the Authentication section.

8. Copy the Primary Key, which serves as your Azure Maps key.
9. Copy/paste the key into the R:BASE PLUGIN command syntax for R:Magellan, specifically for the [KEY](#) parameter.

#### Existing R:Magellan Users

1. The R:BASE PLUGIN command syntax must be updated to replace all instances of "MAP\_ENGINE BING\_MAPS" to "MAP\_ENGINE AZURE\_MAPS".
2. The KEY parameter must also be updated with the newly created Azure Maps key (replacing the Bing Maps key).

## 6.1 Map Calculation

The Map Calculation parameters control how a map route is calculated.

Parameters	Values (bold values are default)	Description
MAP_ENGINE	AZURE_MAPS	Specifies Azure Maps services will be used
KEY	key value	Specifies the API key
ROUTE_CALCULATION	ON OFF	Specifies whether the route is calculated
COORDINATES	value	Specifies latitude and longitude coordinates are used for a location, rather than an address
DIRECTIONS_FILE	file name	Specifies the file name to load the turn by turn navigation. The output can be in XML or CSV format depending on destination file extension.
DEGREES	ON OFF	Specifies if the latitude/longitude return variables are returned as degrees (ON) or a DOUBLE data type values (OFF).
OPTIMIZATION	ON OFF	Specifies whether optimization is used. With optimization set ON, you can reorder the intermediate stops on your route so that your travel time between the start and end points is the most time-efficient.
ROUTE_OPTIMIZATION_TYPE	DISTANCE TIME TIME_WITH_TRAFFIC	Specifies to optimize the route using the shortest distance, the shortest time, or shortest time with traffic
SHOW_PROGRESS	ON OFF	Specifies whether a progress window is displayed while calculations are processing.
SHOW_MAP	ON OFF	Specifies whether the map will be displayed (required for Google Maps)
WINDOW_STATE	MINIMIZED MAXIMIZED NORMAL	Specifies the R:Magellan window state when the map is displayed
FORM_CAPTION	value	Specifies text to appear in the form caption after "R:Magellan"
TRIPINFO_BAR	ON OFF	Specifies to display the "Trip Information" bar which contains details for each waypoint
NAVIGATION_BAR	ON OFF	Specifies to display the "Navigation" bar which contains details for each waypoint. The Navigation bar will only display if the TRIPINFO_BAR parameter is also ON.
Waypoint	value	<p>The waypoint address can be defined as a valid street address or by Latitude and Longitude coordinates.</p> <p>When assigning a route, the waypoint addresses should be listed from start to finish in the order of arrival. The starting and ending points, would be listed first and last. Or, you could use the OPTIMIZATION parameter above.</p>

		<p>The street address value must contain a street number and name followed by a comma, then the city followed by another comma, and then the state and zip code. A correct address parameter example for R:BASE Technologies, Inc. is:</p> <p style="text-align: center;"><a href="#">3935 Old William Penn Highway, Murrysville, PA 15668</a></p> <p>The above street address format is specific to the United States. In other countries, the address format will vary. For example, the address format for a waypoint address in Sweden would begin with the street name and street number followed by a comma, then the zip code, followed by another comma, and then the city:</p> <p style="text-align: center;"><a href="#">Hästholmsvägen 32, 131 30, NACKA</a></p> <p>The waypoint address can also be defined as latitude and longitude coordinates. The coordinates must be defined in the decimal format, but as the TEXT data type. The accuracy of your location depends on the number of decimal values.</p> <p style="text-align: center;"><a href="#">COORDINATES 24.54410,-81.80530</a></p>
--	--	---

## 6.2 Return Variables

After the Plugin is launched, return variables are calculated for the total distance, trip duration, driving time, an estimated trip cost, longitude and latitude for each address, the origin address and destination addresses, the distance traveled between the addresses, and the number of addresses provided. The first address listed is the origin. Each following address provided will be listed a destination on the map, incrementing by 1. A latitude and longitude variable is generated for each address given.

A distance variable is generated from the origin to the first destination. For each additional address provided, a distance variable is generated between those destinations. An elapsed distance is also provided from the origin to each destination on the route. The number of variables returned depend on the number of address parameters you insert into the PLUGIN command.

Variable Name	Data Type	Description
vDrivingDistance	DOUBLE	Total trip distance in miles
vTripDuration	INTEGER	Total trip duration in minutes
vOriginLat	TEXT	Latitude coordinate for the origin
vOriginLong	TEXT	Longitude coordinate for origin
vOriginAddress	TEXT	Address for origin
vDest1Lat	TEXT	Latitude coordinate for first destination
vDest1Long	TEXT	Longitude coordinate for first destination
vDest1Addr	TEXT	Address for first destination
vDest2Lat	TEXT	Latitude coordinate for second destination
vDest2Long	TEXT	Longitude coordinate for second destination
vDest2Addr	TEXT	Address for second destination
vDest1Dist	DOUBLE	Distance in miles from origin to first destination
vDest2Dist	DOUBLE	Distance in miles from first destination to second
vDest1Elapsed	DOUBLE	Distance in miles from origin to first destination
vDest2Elapsed	DOUBLE	Distance in miles from origin to second destination
vDestCount	INTEGER	Number of addresses in map route
vResolvedAddr	TEXT	If a calculated route contains invalid waypoints, where resolved addresses were selected with the "Use Address" button, the variable will contain a text string of the address variable names that were resolved, (e.g. 'vDest3Addr,vDest5Addr'). If vResolvedAddr is NULL, then no invalid and resolved address processes occurred.
vNavURL	TEXT	URL based on the waypoints, which can be sent by email to a driver's phone for navigation

### Miles/Kilometers

The driving distance is provided in miles by default. If the kilometers unit is required, the global variable RMAGELLAN\_DIST\_UNIT can be used to modify the vDrivingDistance end result. If RMAGELLAN\_DIST\_UNIT is set to 'KM', then distances will be provided in kilometers. Any value other than 'KM' (including NULL or if the variable is undefined) will result to distances expressed in miles. Example:

```
SET VAR RMAGELLAN_DIST_UNIT TEXT = 'KM'
```

## 6.3 Examples

### 6.3.1 Example 1

```
-- To launch a mapped route from the prior Microrim headquarters to the
-- prior R:BASE Technologies, Inc. headquarters and save the directions to a file
```

```
SET VAR vStartAddress TEXT = +
'15395 SE 30th Place, Bellevue, WA 98007'

SET VAR vEndAddress TEXT = +
'3935 Old William Penn Highway, Murrysville, PA 15668'

SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE AZURE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|SHOW_MAP ON +
|TRIPINFO_BAR ON +
|NAVIGATION_BAR OFF +
|FORM_CAPTION From Microrim to R:BASE Technologies +
|DIRECTIONS_FILE C:\Directions\Trip_01.xml +
|ROUTE_CALCULATION ON|' + .vStartAddress + '|' + .vEndAddress)
&vPlugin
CLEAR VAR vPlugin, vStartAddress, vEndAddress
RETURN
```

The following variables are returned:


vNavURL	= http://bing.com/maps/default.aspx?mode=D&rtp=pos.47.582169_-122.136579_15395+SE+30th+Pl%2C+Bellevue%2C+WA+98007~pos.40.428069_-79.695865_3935+Old+William+Penn+Hwy%2C+Murrysville%2C+PA+15668	TEXT
vDrivingDistance	= 2526.2	DOUBLE
vTripDuration	= 2040	INTEGER
vDrivingTime	= 2040	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= 15395 SE 30th Pl, Bellevue, WA 98007	TEXT
vDest1Addr	= 3935 Old William Penn Hwy, Murrysville, PA 15668	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 47.582169° North	TEXT

```

vDest1Lat      = 40.428069° North      TEXT
vOriginLong    = 122.136579° West      TEXT
vDest1Long     = 79.695865° West       TEXT
vDest1Elapsed  = 2526.2                 DOUBLE
vDest1Dist     = 2526.2                 DOUBLE
vDestCount     = 2                     INTEGER
vResult        = OK                     TEXT

```

The following map is launched:



### 6.3.2 Example 2

```
-- To launch a mapped route from the western most point in the
-- United States (contiguous) to the Alamo in Texas, to the steps
-- of the U.S. Supreme Court, to the southern most point of the
-- United States (contiguous)
```

```
SET VAR vStartAddress TEXT = +
'COORDINATES 48.16350,-124.7310'
```

```
SET VAR vSecondAddress TEXT = +
'300 Alamo Plaza, San Antonio, Texas 78205'
```

```
SET VAR vThirdAddress TEXT = +
```

```
'131 1st Street, Washington, DC 20002'
```

```
SET VAR vEndAddress TEXT = +
'COORDINATES 24.5441,-81.8053'
```

```
SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE AZURE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|FORM_CAPTION Travel USA +
|SHOW_MAP ON+
|TRIPINFO_BAR ON +
|NAVIGATION_BAR ON +
|ROUTE_CALCULATION ON +
|SHOW_PROGRESS OFF|' + +
.vStartAddress + '|' + .vSecondAddress + '|' + .vThirdAddress + '|' +
.vEndAddress)
&vPlugin
CLEAR VAR vPlugin, vStartAddress, vSecondAddress, vThirdAddress,
vEndAddress
RETURN
```

The following variables are returned:


vNavURL	= http://bing.com/maps/default.aspx?mode=D&rtp=pos.47.925878_-124.6409_Pacific+Northwest+National+Scenic+Trail%2C+Sekiu%2C+WA+98381~pos.29.425706_-98.486101_300+Alamo+Plaza%2C+San+Antonio%2C+TX+78205~pos.38.905143_-77.00412_131+1st+St+NE%2C+Washington%2C+DC+20002~pos.24.5441_-81.8053_24.5441%2C-81.8053	TEXT
vDrivingDistance	= 5107.5	DOUBLE
vTripDuration	= 4437	INTEGER
vDrivingTime	= 4437	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= Pacific Northwest National Scenic Trail, Sekiu, WA 98381, United States	TEXT
vDest1Addr	= 300 Alamo Plaza, San Antonio, TX 78205	TEXT
vDest2Addr	= 131 1st St NE, Washington, DC 20002	TEXT
vDest3Addr	= 24.5441,-81.8053	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 48.1635° North	TEXT
vDest1Lat	= 29.425706° North	TEXT
vDest2Lat	= 38.905143° North	TEXT
vDest3Lat	= 24.545743° North	TEXT
vOriginLong	= 124.731° West	TEXT
vDest1Long	= 98.486101° West	TEXT
vDest2Long	= 77.00412° West	TEXT
vDest3Long	= 81.804582° West	TEXT



```

vDest1Elapsed      = 2286.5          DOUBLE
vDest1Dist         = 2286.5          DOUBLE
vDest2Elapsed      = 3895.3          DOUBLE
vDest2Dist         = 1608.8          DOUBLE
vDest3Elapsed      = 5107.5          DOUBLE
vDest3Dist         = 1212.2          DOUBLE
vDestCount         = 4              INTEGER
vResult            = OK              TEXT

```



### 6.3.3 Example 3

-- To launch a mapped route from the Pittsburgh International Airport  
 -- to the R:BASE Conference, with degrees turned off

```

SET VAR vStartAddress TEXT = +
'COORDINATES 40.49620,-80.25425'

SET VAR vEndAddress TEXT = +
'3962 William Penn Highway, Monroeville, PA 15146'

SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE AZURE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +

```

```


|OPTIMIZATION ON +
|SHOW_MAP ON +
|TRIPINFO_BAR ON +
|NAVIGATION_BAR ON +
|FORM_CAPTION From Airport to the R:BASE Conference +
|DEGREES OFF|' + .vStartAddress + '|' + .vEndAddress)
&vPlugin
CLEAR VAR vPlugin, vStartAddress, vEndAddress
RETURN

```

The following variables are returned:

vNavURL	= http://bing.com/maps/default.aspx?mode=D&rtp=pos.40.496208_-80.25502_1001+Airport+Blvd%2C+Pittsburgh%2C+PA+15231~pos.40.437203_-79.773299_3962+William+Penn+Hwy%2C+Monroeville%2C+PA+15146	TEXT
vDrivingDistance	= 31.8	DOUBLE
vTripDuration	= 35	INTEGER
vDrivingTime	= 35	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= 1001 Airport Blvd, Pittsburgh, PA 15231, United States	TEXT
vDest1Addr	= 3962 William Penn Hwy, Monroeville, PA 15146	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 40.496208	DOUBLE
vDest1Lat	= 40.437203	DOUBLE
vOriginLong	= -80.25502	DOUBLE
vDest1Long	= -79.773299	DOUBLE
vDest1Elapsed	= 31.8	DOUBLE
vDest1Dist	= 31.8	DOUBLE
vDestCount	= 2	INTEGER
vResult	= OK	TEXT

The following map is launched:



### 6.3.4 Example 4

-- To launch a map displaying a single address

```
SET VAR vSingleAddress TEXT = +
'114 N Main St, Roswell, NM 88203'


SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE AZURE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|SHOW_MAP ON +
|TRIPINFO_BAR OFF +
|NAVIGATION_BAR OFF +
|FORM_CAPTION Single Address +
|' + .vSingleAddress)
&vPlugin
CLEAR VAR vPlugin, vSingleAddress
RETURN
```

The following variables are returned:

```
vNavURL = http://bing.com/maps/default.a TEXT
```

	spx?mode=D&rtp=pos.33.393706_-104.522974_114+N+Main+St%2C+Roswell%2C+NM+88203	
vDrivingDistance	= 0.	DOUBLE
vTripDuration	= 0	INTEGER
vDrivingTime	= 0	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= 114 N Main St, Roswell, NM 88203	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 33.393706° North	TEXT
vOriginLong	= 104.522974° West	TEXT
vDestCount	= 1	INTEGER
vResult	= OK	TEXT

The following map is launched:



**Part**

**VII**

## 7 Working With Google Maps

The following details the specific use of R:Magellan with Google Maps.

### Syntax:

```
PLUGIN RMagellan 'VarName|<Parameter Value>'
```

### Where:

"**VarName**" is the resulting text variable which returns the status, such as 'OK' or the exact -ERROR- message.

"**Parameter**" is the available option recognized by the Plugin.

"**Value**" is the specific value used by the available parameter.

### Notes:

- The R:Magellan parameters can be any number of values, but a starting location and ending location must be specified in order for a mapped route to be provided. Each address parameter must be separated with the pipe "|" character.
- A Google Maps "Directions API" key must be acquired and included with the PLUGIN syntax in order to use Google's map and direction services with R:Magellan. See "Accessing Google MAP Services" below.
- In order to utilize Google Maps, the OpenSSL Project files must installed on the computer as HTTPS is now a requirement of the map and geolocation APIs.

#### OpenSSL:

The OpenSSL Project is a collaborative effort to develop a robust, commercial-grade, full-featured, and Open Source toolkit implementing the Secure Sockets Layer (SSL v2/v3) and Transport Layer Security (TLS v1) protocols.

<http://www.openssl.org/>


#### Win32 OpenSSL:

Although the above site is Open Source, it is not user friendly as far as a Windows installation for general use. The Win32 OpenSSL Installation Project is dedicated to providing a simple installation of OpenSSL. It is easy to set up and easy to use through the simple, effective installer. Regardless of the Windows operating system, the Win32 installer must be used, not Win64.

<http://www.slproweb.com/products/Win32OpenSSL.html>

Once the OpenSSL libraries are installed, the required DLLs, libeay32.dll and ssleay32.dll, must be placed in the the R:BASE 11 program directory or the runtime/compiled application directory. Although the DLLs may be placed into the operating system folder, it is advised to put the OpenSSL DLLs in the same folder as the applications that will use them. The reason is that different programs may have different SSL requirements.

- All PLUGIN commands MUST use the "SHOW\_MAP ON" parameter, so a graphical map is displayed. This is Google's requirement. Using Directions data without displaying a map for which directions data was requested is prohibited. Additionally, calculation of directions generates copyrights and warnings which must be displayed to the user in some fashion. Additional information regarding the Directions API is available at the following URL:  
<https://developers.google.com/maps/documentation/directions/intro/>
- In the event an address or coordinates has multiple hits or is invalid, the "Find Address" dialog will be displayed to specify a different address. The "Address" field and "Find" button can be used to perform multiple searches for repeated search inquiries, where the user can enhance the address field contents to pinpoint the desired destination. Once a desired address is located and highlighted, the "Use Address" button is selected to use that destination.



## Accessing Google Maps Platform

### New R:Magellan Users

1. A Google account (GMail, etc.) must be created to access Google services and to use the Google Maps Platform. Please visit the following URL to log in or to create an account:  
<https://accounts.google.com/>
2. After an account is created, visit the Developers Console to create a project. Please visit:  
<https://console.cloud.google.com/google/maps-apis/api-list>
3. Only the Routes API is needed to use Google Maps with R:Magellan (Google Maps > APIs and Services > Routes API).
4. Enable the Routes API and create an API key.
5. Copy/paste the key into the R:BASE PLUGIN syntax for R:Magellan, specifically for the [KEY](#) parameter.

### Existing R:Magellan Users

#### Using the Directions API

R:Magellan users with applications using the Directions API will be forced to eventually upgrade to the Routes API. The restriction imposed is that the Directions API can no longer be activated. Existing Google accounts already using the Directions API service are not affected. Currently, no time frame has been announced when the Directions API service will be taken down. As a result, existing R:Magellan users with a Google key with the Directions API are not affected.

#### Using the Route API

Google Maps user can now add/enable the Routes API to their existing key (in the Google Developers Console).

1. Log onto your Google account and visit the Developers Console:  
<https://console.cloud.google.com/google/maps-apis/api-list>
2. Edit your existing key
3. Enable the "Routes API" in the "API restrictions" section
4. Press the "Save" button

To offer a seamless transition from the Directions API to the Routes API, the `RM_GROUTE_API` variable has been introduced. During application startup, the variable must be set to 'ON'. When ON, R:Magellan will use the Routes API instead of Directions API, allowing the existing application to be used without having to update the KEY parameter for the PLUGIN command(s).

```
SET VAR RM_GROUTE_API TEXT = 'ON'
```



## 7.1 Map Calculation

The Map Calculation parameters control how a map route is calculated.

Parameters	Values (bold values are default)	Description
MAP_ENGINE	GOOGLE_MAPS	Specifies Google Maps services will be used
KEY	key value	Specifies the API key
ROUTE_CALCULATION	ON OFF	Specifies whether the route is calculated
COORDINATES	value	Specifies latitude and longitude coordinates are used for a location, rather than an address
DIRECTIONS_FILE	file name	Specifies the file name to load the turn by turn navigation. The output can be in XML or CSV format depending on destination file extension.
DEGREES	<b>ON</b> OFF	Specifies if the latitude/longitude return variables are returned as degrees (ON) or a DOUBLE data type values (OFF).
OPTIMIZATION	ON OFF	Specifies whether optimization is used. With optimization set ON, you can reorder the intermediate stops on your route so that your travel time between the start and end points is the most time-efficient.
SHOW_PROGRESS	ON <b>OFF</b>	Specifies whether a progress window is displayed while calculations are processing.
SHOW_MAP	ON OFF	Specifies whether the map will be displayed (required for Google Maps)
WINDOW_STATE	MINIMIZED MAXIMIZED <b>NORMAL</b>	Specifies the R:Magellan window state when the map is displayed
FORM_CAPTION	value	Specifies text to appear in the form caption after "R:Magellan"
TRIPINFO_BAR	ON <b>OFF</b>	Specifies to display the "Trip Information" bar which contains details for each waypoint
NAVIGATION_BAR	ON <b>OFF</b>	Specifies to display the "Navigation" bar which contains details for each waypoint. The Navigation bar will only display if the TRIPINFO_BAR parameter is also ON.

Waypoint	value	<p>The waypoint address can be defined as a valid street address or by Latitude and Longitude coordinates.</p> <p>When assigning a route, the waypoint addresses should be listed from start to finish in the order of arrival. The starting and ending points, would be listed first and last. Or, you could use the OPTIMIZATION parameter above.</p> <p>The street address value must contain a street number and name followed by a comma, then the city followed by another comma, and then the state and zip code. A correct address parameter example for R:BASE Technologies, Inc. is:</p> <p style="text-align: center;"><a href="#">3935 Old William Penn Highway, Murrysville, PA 15668</a></p> <p>The above street address format is specific to the United States. In other countries, the address format will vary. For example, the address format for a waypoint address in Sweden would begin with the street name and street number followed by a comma, then the zip code, followed by another comma, and then the city:</p> <p style="text-align: center;"><a href="#">Hästholsvägen 32, 131 30, NACKA</a></p> <p>The waypoint address can also be defined as latitude and longitude coordinates. The coordinates must be defined in the decimal format, but as</p>
----------	-------	---



		the TEXT data type. The accuracy of your location depends on the number of decimal values.
		COORDINATES 24.54410,-81.80530

## 7.2 Return Variables

After the Plugin is launched, return variables are calculated for the total distance, trip duration, driving time, an estimated trip cost, longitude and latitude for each address, the origin address and destination addresses, the distance traveled between the addresses, and the number of addresses provided. The first address listed is the origin. Each following address provided will be listed a destination on the map, incrementing by 1. A latitude and longitude variable is generated for each address given.

A distance variable is generated from the origin to the first destination. For each additional address provided, a distance variable is generated between those destinations. An elapsed distance is also provided from the origin to each destination on the route. The number of variables returned depend on the number of address parameters you insert into the PLUGIN command.


Variable Name	Data Type	Description
vDrivingDistance	DOUBLE	Total trip distance in miles
vTripDuration	INTEGER	Total trip duration in minutes
vOriginLat	TEXT	Latitude coordinate for the origin
vOriginLong	TEXT	Longitude coordinate for origin
vOriginAddress	TEXT	Address for origin
vDest1Lat	TEXT	Latitude coordinate for first destination
vDest1Long	TEXT	Longitude coordinate for first destination
vDest1Addr	TEXT	Address for first destination
vDest2Lat	TEXT	Latitude coordinate for second destination
vDest2Long	TEXT	Longitude coordinate for second destination
vDest2Addr	TEXT	Address for second destination
vDest1Dist	DOUBLE	Distance in miles from origin to first destination
vDest2Dist	DOUBLE	Distance in miles from first destination to second
vDest1Elapsed	DOUBLE	Distance in miles from origin to first destination
vDest2Elapsed	DOUBLE	Distance in miles from origin to second destination
vDestCount	INTEGER	Number of addresses in map route
vResolvedAddr	TEXT	If a calculated route contains invalid waypoints, where resolved addresses were selected with the "Use Address" button, the variable will contain a text string of the address variable names that were resolved, (e.g. 'vDest3Addr,vDest5Addr'). If vResolvedAddr is NULL, then no invalid and resolved address processes occurred.
vNavURL	TEXT	URL based on the waypoints, which can be sent by email to a driver's phone for navigation

### Miles/Kilometers

The driving distance is provided in miles by default. If the kilometers unit is required, the global variable RMAGELLAN\_DIST\_UNIT can be used to modify the vDrivingDistance end result. If RMAGELLAN\_DIST\_UNIT is set to 'KM', then distances will be provided in kilometers. Any value other than 'KM' (including NULL or if the variable is undefined) will result to distances expressed in miles. Example:

```
SET VAR RMAGELLAN_DIST_UNIT TEXT = 'KM'
```





### 7.3.2 Example 2

- To launch a mapped route from the western most point in the
- United States (contiguous) to the Alamo in Texas, to the steps
- of the U.S. Supreme Court, to the southern most point of the
- United States (contiguous)

```
SET VAR vStartAddress TEXT = +
'COORDINATES 48.16350,-124.7310'
```

```
SET VAR vSecondAddress TEXT = +
'300 Alamo Plaza, San Antonio, Texas 78205'
```

```
SET VAR vThirdAddress TEXT = +
'131 1st Street, Washington, DC 20002'
```

```
SET VAR vEndAddress TEXT = +
'COORDINATES 24.5441,-81.8053'
```

```
SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE GOOGLE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|SHOW_MAP ON +
|TRIPINFO_BAR ON +
|NAVIGATION_BAR ON +
|ROUTE_CALCULATION ON +
|SHOW_PROGRESS OFF|' + +
.vStartAddress + '|' + .vSecondAddress + '|' + .vThirdAddress + '|' +
.vEndAddress)
```

&vPlugin


**CLEAR VAR** vPlugin, vStartAddress, vSecondAddress, vThirdAddress, vEndAddress

**RETURN**

The following variables are returned:

vNavURL	= https://www.google.com/maps/dir/Pacific+NW+Trail%2C+Clallam+Bay%2C+WA+98326%2C+USA/300+Alamo+Plaza%2C+San+Antonio%2C+TX+78205%2C+USA/131+First+St+NW%2C+Washington%2C+DC+20004%2C+USA/Fort+Zachary+Taylor%2C+Key+West%2C+FL+33040%2C+USA/am=t/	TEXT
vDrivingDistance	= 4967.1	DOUBLE
vTripDuration	= 4448	INTEGER
vDrivingTime	= 4448	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= Pacific NW Trail, Clallam Bay, WA 98326, USA	TEXT
vDest1Addr	= 300 Alamo Plaza, San Antonio, TX 78205, USA	TEXT
vDest2Addr	= 131 First St NW, Washington, DC 20004, USA	TEXT
vDest3Addr	= Fort Zachary Taylor, Key West, FL 33040, USA	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 48.16376° North	TEXT
vDest1Lat	= 29.425837° North	TEXT
vDest2Lat	= 38.89166° North	TEXT
vDest3Lat	= 24.548418° North	TEXT
vOriginLong	= 124.733144° West	TEXT
vDest1Long	= 98.486912° West	TEXT
vDest2Long	= 77.012158° West	TEXT
vDest3Long	= 81.808953° West	TEXT
vDest1Elapsed	= 2149.	DOUBLE
vDest1Dist	= 2149.	DOUBLE
vDest2Elapsed	= 3754.9	DOUBLE
vDest2Dist	= 1605.9	DOUBLE
vDest3Elapsed	= 4967.1	DOUBLE
vDest3Dist	= 1212.2	DOUBLE
vDestCount	= 4	INTEGER
vResult	= OK	TEXT

The following map is launched:



### 7.3.3 Example 3

- To launch a mapped route from the Pittsburgh International Airport
- to the R:BASE Conference, with degrees turned off

```
SET VAR vStartAddress TEXT = +
'COORDINATES 40.49620,-80.25425'

SET VAR vEndAddress TEXT = +
'3962 William Penn Highway, Monroeville, PA 15146'


SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE GOOGLE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|SHOW_MAP ON +
|TRIPINFO_BAR ON +
|NAVIGATION_BAR ON +
|FORM_CAPTION From Airport to the R:BASE Conference +
|DEGREES OFF|' + .vStartAddress + '|' + .vEndAddress)
&vPlugin
```

**RETURN**

The following variables are returned:

vNavURL	= https://www.google.com/maps/dir/Alternate+Security+Checkpoint%2C+1000+Airport+Blvd%2C+Pittsburgh%2C+PA+15231%2C+USA/3962+William+Penn+Hwy%2C+Monroeville%2C+PA+15146%2C+USA/am=t/	TEXT
vDrivingDistance	= 33.7	DOUBLE
vTripDuration	= 44	INTEGER
vDrivingTime	= 44	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= Alternate Security Checkpoint, 1000 Airport Blvd, Pittsburgh, PA 15231, USA	TEXT
vDest1Addr	= 3962 William Penn Hwy, Monroeville, PA 15146, USA	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 40.496048	DOUBLE
vDest1Lat	= 40.437109	DOUBLE
vOriginLong	= -80.254848	DOUBLE
vDest1Long	= -79.773682	DOUBLE
vDest1Elapsed	= 33.7	DOUBLE
vDest1Dist	= 33.7	DOUBLE
vDestCount	= 2	INTEGER
vResult	= OK	TEXT

The following map is launched:



### 7.3.4 Example 4

-- To launch a map displaying a single address

```
SET VAR vSingleAddress TEXT = +
'114 N Main St, Roswell, NM 88203'

SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE GOOGLE_MAPS +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|SHOW_MAP ON +
|TRIPINFO_BAR OFF +
|NAVIGATION_BAR OFF +
|FORM_CAPTION Single Address +
|' + .vSingleAddress)
&vPlugin
RETURN
```


The following variables are returned:

```
vNavURL = https://www.google.com/maps/di TEXT
```



	r/114+N+Main+St%2C+Roswell%2C+NM+88203%2C+USA/am=t/	
vDrivingDistance	= 0.	DOUBLE
vTripDuration	= 0	INTEGER
vDrivingTime	= 0	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddr	= 114 N Main St, Roswell, NM 88203, USA	TEXT
vResolvedAddr	=	TEXT
vOriginLat	= 33.39367° North	TEXT
vOriginLong	= 104.523017° West	TEXT
vDestCount	= 1	INTEGER
vResult	= OK	TEXT

The following map is launched:





**Part**

**VIII**

## 8 Working With MapQuest

The following details the specific use of R:Magellan with MapQuest.

### Syntax:

```
PLUGIN RMagellan 'VarName|<Parameter Value>'
```

### Where:

"**VarName**" is the resulting text variable which returns the status, such as 'OK' or the exact -ERROR- message.

"**Parameter**" is the available option recognized by the Plugin.

"**Value**" is the specific value used by the available parameter.

### Notes:

- The R:Magellan parameters can be any number of values, but a starting location and ending location must be specified in order for a mapped route to be provided. Each address parameter must be separated with the pipe "|" character.
- A MapQuest "Consumer Key" must be acquired and included with the PLUGIN syntax in order to use MapQuest's direction services with R:Magellan. See "Accessing MapQuest Services" below.
- The SHOW\_MAP parameter is not supported in MapQuest, so a visual representation of the entered route will not be displayed.

### Accessing MapQuest Services

1. An account must be created to access MapQuest services. Please visit: [https://developer.mapquest.com/plan\\_purchase/steps/business\\_edition/business\\_edition\\_free](https://developer.mapquest.com/plan_purchase/steps/business_edition/business_edition_free)
2. Fill in the required fields to create an account.
3. After the account setup is complete, go to "Keys & Reporting" and click "My Application" or any application. The "Consumer Key" is the key needed for R:Magellan.
4. Copy/paste the key into the R:BASE PLUGIN syntax for R:Magellan, specifically for the [KEY](#) parameter.

## 8.1 Map Calculation

The Map Calculation parameters control how a map route is calculated.

Parameters	Values (bold values are default)	Description
MAP_ENGINE	MAP_REQUEST	Specifies MapQuest services will be used
KEY	key value	Specifies the consumer key
ROUTE_CALCULATION	ON OFF	Specifies whether the route is calculated
COORDINATES	value	Specifies latitude and longitude coordinates are used for a location, rather than an address
DIRECTIONS_FILE	file name	Specifies the file name to load the turn by turn navigation. The output can be in XML or CSV format depending on destination file extension.
DEGREES	ON OFF	Specifies if the latitude/longitude return variables are returned as degrees (ON) or a DOUBLE data type values (OFF).
OPTIMIZATION	ON OFF	Specifies whether optimization is used. With optimization set ON, you can reorder the intermediate stops on your

		route so that your travel time between the start and end points is the most time-efficient.
ROUTE_OPTIMIZATION_TYPE	DISTANCE TIME	Specifies to optimize the route using the shortest distance or the shortest time
SHOW_PROGRESS	ON OFF	Specifies whether a progress window is displayed while calculations are processing.
WINDOW_STATE	MINIMIZED MAXIMIZED NORMAL	Specifies the R:Magellan window state when the map is displayed

Waypoint	value	<p>The waypoint address can be defined as a valid street address or by Latitude and Longitude coordinates.</p> <p>When assigning a route, the waypoint addresses should be listed from start to finish in the order of arrival. The starting and ending points, would be listed first and last. Or, you could use the OPTIMIZATION parameter above.</p> <p>The street address value must contain a street number and name followed by a comma, then the city followed by another comma, and then the state and zip code. A correct address parameter example for R:BASE Technologies, Inc. is:</p> <p style="text-align: center;"><a href="#">3935 Old William Penn Highway, Murrys ville, PA 15668</a></p> <p>The above street address format is specific to the United States. In other countries, the address format will vary. For example, the address format for a waypoint address in Sweden would begin with the street name and street number followed by a comma, then the zip code, followed by another comma, and then the city:</p> <p style="text-align: center;"><a href="#">Hästh olmsv ägen 32, 131 30, NACKA</a></p> <p>The waypoint address can also be defined as latitude and longitude coordinates. The coordinates must be defined in the decimal format, but as the TEXT data type. The accuracy of your location depends on the number of decimal values.</p> <p style="text-align: center;"><a href="#">COORDINATES 24.54410,-81.80530</a></p>
----------	-------	--

## 8.2 Return Variables

After the Plugin is launched, return variables are calculated for the total distance, trip duration, driving time, an estimated trip cost, longitude and latitude for each address, the origin address and destination addresses, the distance traveled between the addresses, and the number of addresses provided. The first address listed is the origin. Each following address provided will be listed a destination on the map, incrementing by 1. A latitude and longitude variable is generated for each address given.

A distance variable is generated from the origin to the first destination. For each additional address provided, a distance variable is generated between those destinations. An elapsed distance is also provided from the origin to each destination on the route. The number of variables returned depend on the number of address parameters you insert into the PLUGIN command.

Variable Name	Data Type	Description
vDrivingDistance	DOUBLE	Total trip distance in miles
vTripDuration	INTEGER	Total trip duration in minutes
vOriginLat	TEXT	Latitude coordinate for the origin
vOriginLong	TEXT	Longitude coordinate for origin
vOriginAddress	TEXT	Address for origin
vDest1Lat	TEXT	Latitude coordinate for first destination
vDest1Long	TEXT	Longitude coordinate for first destination



vDest1Long	= 79.695846° West	TEXT
vDest1Elapsed	= 2531.	DOUBLE
vDest1Dist	= 2531.	DOUBLE
vDestCount	= 2	INTEGER
vResult	= OK	TEXT

### 8.3.2 Example 2

```
-- To launch a mapped route from the western most point in the
-- United States (contiguous) to the Alamo in Texas, to the steps
-- of the U.S. Supreme Court, to the southern most point of the
-- United States (contiguous)
```

```
SET VAR vStartAddress TEXT = +
'COORDINATES 48.16350,-124.7310'
```

```
SET VAR vSecondAddress TEXT = +
'300 Alamo Plaza, San Antonio, Texas 78205'
```

```
SET VAR vThirdAddress TEXT = +
'131 1st Street, Washington, DC 20002'
```

```
SET VAR vEndAddress TEXT = +
'COORDINATES 24.5441,-81.8053'
```

```
SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE MAP_QUEST +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|OPTIMIZATION ON
|ROUTE_OPTIMIZATION_TYPE DISTANCE +
|ROUTE_CALCULATION ON +
|SHOW_PROGRESS OFF|' + +
.vStartAddress + '|' + .vSecondAddress + '|' + .vThirdAddress + '|' +
.vEndAddress)
&vPlugin
CLEAR VAR vPlugin, vStartAddress, vSecondAddress, vThirdAddress,
vEndAddress
RETURN
```

The following variables are returned:

vDrivingDistance	= 4930.	DOUBLE
vTripDuration	= 4708	INTEGER
vDrivingTime	= 4708	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddress	= Pacific NW Trail, Clallam Bay, WA 98326, USA	TEXT
vDest1Addr	= 300 Alamo Plaza, San Antonio, TX 78205, USA	TEXT
vDest2Addr	= 131 First St NE, Washington, DC 20543, USA	TEXT
vDest3Addr	= Covington Ave, Key West, FL 33040, USA	TEXT
vOriginLat	= 48.147621° North	TEXT
vDest1Lat	= 29.425672° North	TEXT

vDest2Lat	= 38.890605° North	TEXT
vDest3Lat	= 24.570955° North	TEXT
vOriginLong	= 124.717724° West	TEXT
vDest1Long	= 98.486953° West	TEXT
vDest2Long	= 77.005928° West	TEXT
vDest3Long	= 81.741653° West	TEXT
vDest1Elapsed	= 2159.6	DOUBLE
vDest1Dist	= 2159.6	DOUBLE
vDest2Elapsed	= 3730.4	DOUBLE
vDest2Dist	= 1570.8	DOUBLE
vDest3Elapsed	= 4930.	DOUBLE
vDest3Dist	= 1199.6	DOUBLE
vDestCount	= 4	INTEGER
vResult	= OK	TEXT

### 8.3.3 Example 3

-- To launch a mapped route from the Pittsburgh International Airport  
 -- to the R:BASE Conference, with degrees turned off

```
SET VAR vStartAddress TEXT = +
'COORDINATES 40.49620,-80.25425'

SET VAR vEndAddress TEXT = +
'3962 William Penn Highway, Monroeville, PA 15146'

SET VAR vPlugin TEXT = +
('PLUGIN RMagellan vResult +
|MAP_ENGINE MAP_QUEST +
|KEY xxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx +
|DEGREES OFF|' + .vStartAddress + '|' + .vEndAddress)
&vPlugin
RETURN
```

The following variables are returned:

vDrivingDistance	= 29.1	DOUBLE
vTripDuration	= 36	INTEGER
vDrivingTime	= 36	INTEGER
vTripCost	= \$0.00	CURRENCY
vOriginAddress	= Airport Blvd, Coraopolis, PA 15108, USA	TEXT
vDest1Addr	= 3962 William Penn Hwy, Monroeville, PA 15146, USA	TEXT
vOriginLat	= 40.496615	DOUBLE
vDest1Lat	= 40.438224	DOUBLE
vOriginLong	= -80.255609	DOUBLE
vDest1Long	= -79.773498	DOUBLE
vDest1Elapsed	= 29.1	DOUBLE
vDest1Dist	= 29.1	DOUBLE
vDestCount	= 2	INTEGER
vResult	= OK	TEXT

**Part**

**IX**

## 9 Find Address Utility

A Find Address utility is available to check if an address can be located. The search can be performed with an address or Latitude and Longitude coordinates. An address search may also be performed in "silent" mode to hide the "Find Address" dialog.

It is a good idea to check if an address can be resolved before using R:Magellan to calculate trips, allowing you to update the address table data when necessary.

### Syntax:

```
PLUGIN RMagellan VarName|FIND_ADDRESS|<Parameter Value>'
```

### Where:

"**VarName**" is the resulting text variable which returns the status, such as 'OK' or the exact -ERROR- message.

"**Parameter**" is the available option recognized by the Plugin.

"**Value**" is the specific value used by the available parameter.

### Parameters:

Parameter	Value	Description
MAP_ENGINE	GOOGLE_MAPS AZURE_MAPS	Specifies map service to be used
KEY	value	Specifies the API key
VALUE	value	specifies an address or coordinates
SILENT	ON OFF	specifies to show or hide the "Find Address" dialog

### Return Variables:

Variable Name	Description
vFormattedAddress	returns the resolved address

### Notes:

- The variable and parameter values must be separated by a "|" pipe symbol.
- If vFormattedAddress is NULL, the input address cannot be located.


## 9.1 Examples

### Example 01:

```
--checks latitude and longitude coordinates for a valid destination
--after changing "63.989308" to "73.989308", the first value is selected
```

```
PLUGIN RMAGELLAN vResult +
|FIND_ADDRESS +
|MAP_ENGINE GOOGLE_MAPS +
|KEY XXXXXXXXXXXXXXXXXXXX +
|VALUE 40.741895,-63.989308
```





```

SHOW VAR
vFormattedAddress = 23 St, E 23rd St, New York,          TEXT
                  NY 10010, USA
vResult           = OK                                  TEXT

```

### Example 02:

--checks an address for a valid destination  
 --after changing the city and state from "Lodi, AR" to "Pittsburgh, PA", the first value is selected

```

SET VAR vInvalidEndAddress TEXT = '121 McKnight Road, Lodi, AR 16458'
SET VAR vCommand TEXT = +
('PLUGIN RMagellan vResult +
| FIND_ADDRESS +
| MAP_ENGINE AZURE_MAPS +
| KEY XXXXXXXXXXXXXXXXXXXX +
| VALUE'&.vInvalidEndAddress)
&vCommand
RETURN

```

```

SHOW VAR
vFormattedAddress = McKnight Rd, Pennsylvania, USA      TEXT
vResult           = OK                                  TEXT

```

**Part**

**X**

## 10 Geocoding

The geocoding features of R:Magellan finds latitude and longitude coordinate geographic data from a provided street address. The plugin also provides reverse geocoding where an approximate address is returned with given latitude and longitude coordinates.

### Syntax:

```
PLUGIN RMagellan vResult|GEOCODE|<parameters
```

### Parameters:

Parameter	Value	Description
MAP_ENGINE	GOOGLE_MAPS AZURE_MAPS	Specifies map service to be used
KEY	value	Specifies the API key
DIRECTION	FORWARD (default)  REVERSE	specifies the forward or reverse geocoding direction. With the <b>FORWARD</b> direction, an address is used to find latitude and longitude coordinates. With the <b>REVERSE</b> direction latitude and longitude coordinates are used to find an address.
VALUE	value	specifies an address or coordinates

### Return Variables:

Direction	Variable Name	Description
Forward	vRGLat	returns the latitude
Forward	vRGLng	returns the longitude
Forward/Reverse	vResult	returns the status, such as 'OK' or the exact -ERROR- message
Reverse	VRGAddress	returns the address

### Notes:

- The variable and parameter values must be separated by a "|" pipe symbol.
- When using the FORWARD direction, the latitude and longitude are returned as DOUBLE data type values.
- When using the REVERSE direction, the latitude value must be listed first.
- When using the REVERSE direction, the latitude and longitude values must be separated with a comma.

## 10.1 Examples

### Example 01:

--uses the FORWARD direction to acquire latitude and longitude coordinates

```
SET VAR vAddress TEXT = '3935 Old William Penn Highway, Murrysville, PA 15668 USA'
SET VAR vCommand TEXT = +
('PLUGIN RMagellan vResult +
|GEOCODE +
|MAP_ENGINE GOOGLE_MAPS +
|KEY XXXXXXXXXXXXXXXXXXXX +
|VALUE'&.vAddress)
&vCommand
```

```
RETURN
```

```
SHOW VAR
```

```
vRGLat          = 40.4280498          DOUBLE
vRGLng          = -79.695859          DOUBLE
vResult         = OK                  TEXT
```

**Example 02:**

```
--uses the REVERSE direction to acquire an address
```

```
SET VAR vCoordinates TEXT = '39.631693,-105.117094'
SET VAR vCommand TEXT = +
('PLUGIN RMagellan vResult +
|GEOCODE +
|MAP_ENGINE AZURE_MAPS +
|KEY XXXXXXXXXXXXXXXXXXXX +
|DIRECTION REVERSE +
|VALUE'&.vCoordinates)
&vCommand
RETURN
```

```
SHOW VAR
```

```
vRGAddress      = 10601 W Marlowe Ave,      TEXT
                  Littleton, CO 80127, USA
vResult         = OK                  TEXT
```

**Part**

**XI**

## 11 Technical Support

Please read over the help documentation at least once before seeking support. We have worked very hard to make the help documentation clear and useful, but concise. It is suggested that you reread these instructions once you have become accustomed to using the software, as new uses will become apparent.

If you have further questions, and cannot find the answers in the documentation, you can obtain information from the below sources:

- Email our Technical Support Staff at: [support@rbase.com](mailto:support@rbase.com)
- Access the R:BASE Technologies Support home page online at <https://www.rbase.com/support>

You may be required to purchase a technical support plan. Several support plans are available to suit the needs of all users. [Available Technical Support Plans](#)

Please be prepared to provide the following:

- The product registration number, which is located on the invoice/order slip for the purchased product
- The type of operating system and hardware in use
- Details regarding your operating environment; such as available memory, disk space, your version of R:BASE, local area network, special drivers, related database structures, application files, and other files that are used or accessed by your application

All provide information will be used to better assist you.

R:BASE Technologies has a number of different services available for R:BASE products. As a registered user, you will receive information about new features for R:BASE and other R:BASE Technologies products. Please remember to register your software. <https://www.rbase.com/register/>

**Part**

---

**XII**

## 12 Useful Resources

- . R:BASE Home Page: <https://www.rbase.com>
- . Up-to-Date R:BASE Updates: <https://www.rbaseupdates.com>
- . Current Product Details and Documentation: <https://www.rbase.com/rbg11>
- . Support Home Page: <https://www.rbase.com/support>
- . Product Registration: <https://www.rbase.com/register>
- . Official R:BASE Facebook Page: <https://www.facebook.com/rbase>
- . Sample Applications: <https://www.razzak.com/sampleapplications>
- . Technical Documents (From the Edge): <https://www.razzak.com/fte>
- . Education and Training: <https://www.rbase.com/training>
- . Product News: <https://www.rbase.com/news>
- . Upcoming Events: <https://www.rbase.com/events>
- . R:BASE Online Help Manual: <https://www.rbase.com/support/rsyntax>
- . Form Properties Documentation: <https://www.rbase.com/support/FormProperties.pdf>
- . R:BASE Beginners Tutorial: <https://www.rbase.com/support/rtutorial>
- . R:BASE Solutions (Vertical Market Applications): <https://www.rbase.com/products/rbasesolutions>



**Part**

**XIII**

## 13 Feedback

### **Suggestions and Enhancement Requests:**

From time to time, everyone comes up with an idea for something they'd like a software product to do differently.

If you come across an idea that you think might make a nice enhancement, your input is always welcome.

Please submit your suggestion and/or enhancement request to the R:BASE Developers' Corner Crew (R:DCC) and describe what you think might make an ideal enhancement. In R:BASE, the R:DCC Client is fully integrated to communicate with the R:BASE development team. From the main menu bar, choose "Help" > "R:DCC Client". If you do not have a login profile, select "New User" to create one.

If you have a sample you wish to provide, have the files prepared within a zip archive prior to initiating the request. You will be prompted to upload any attachments during the submission process.

Unless additional information is needed, you will not receive a direct response. You can periodically check the status of your submitted enhancement request.

If you are experiencing any difficulties with the R:DCC Client, please send an e-mail to [rdcc@rbase.com](mailto:rdcc@rbase.com).

### **Reporting Bugs:**

If you experience something you think might be a bug, please report it to the R:BASE Developers' Corner Crew. In R:BASE, the R:DCC Client is fully integrated to communicate with the R:BASE development team. From the main menu bar, choose "Help" > "R:DCC Client". If you do not have a login profile, select "New User" to create one.

You will need to describe:

- What you did, what happened, and what you expected to happen
- The product version and build
- Any error message displayed
- The operating system in use
- Anything else you think might be relevant

If you have a sample you wish to provide, have the files prepared within a zip archive prior to initiating the bug report. You will be prompted to upload any attachments during the submission process.

Unless additional information is needed, you will not receive a direct response. You can periodically check the status of your submitted bug.

If you are experiencing any difficulties with the R:DCC Client, please send an e-mail to [rdcc@rbase.com](mailto:rdcc@rbase.com).

# Index

## - A -

activate 15  
Activation Key 15, 19  
address 24, 40, 52, 62  
Address Validator 23  
API key 39, 50  
area 30  
Azure 39  
Azure MAP Services 39  
Azure Maps 39

## - B -

BALLOON 24

## - C -

caption 24  
collate 30  
command 23, 68, 71  
Computer ID 15  
Consumer Key 62  
copies 30  
copyrights 6  
cost 31

## - D -

data type 31, 41, 53, 63  
deactivation 19  
DEGREES 24, 40, 52, 62  
destination 31, 41, 53, 63  
DIRECTION 71  
Directions API 50  
distance 31  
distance traveled 31, 41, 53, 63  
DOUBLE 71  
driving time 31  
duration 31, 41, 53, 63

## - E -

example 32, 33, 35, 37, 42, 43, 45, 47, 54, 55, 57,  
59, 64, 65, 66, 68, 71

## - F -

fax 30  
feedback 78  
Find Address 68  
FIND\_ADDRESS 68  
FORWARD 71  
fuel cost 24

## - G -

Google 50  
Google MAP Services 50  
Google Maps 50

## - I -

installation 14  
introduction 6

## - K -

key, activation 13  
kilometers 41, 53, 63

## - L -

latitude 24, 31, 40, 41, 52, 53, 62, 63, 68, 71  
legend 30  
license 7, 13  
License Key 15, 17, 19  
license transfer 19  
load map 29  
longitude 24, 31, 40, 41, 52, 53, 62, 63, 68, 71

## - M -

map calculation 24, 40, 52, 62  
map style 29

MapPoint 23  
MapQuest 62  
miles 41, 53, 63

## - N -

NAME 24

## - O -

optimization 24, 40, 52, 62  
orientation 30

## - P -

parameter 23, 24, 29, 40, 52, 62, 68, 71  
PLUGIN 23, 68, 71  
Plugin File 17  
printing 30  
progress 24, 40, 52, 62  
PROPERTY 17

## - Q -

quality 30

## - R -

R:Compiler 17  
register 15  
registration number 13  
requirements 14  
resolution 30  
return variable 31, 41, 53, 63  
REVERSE 71  
route cost 24  
route itinerary 29  
Runtime 17

## - S -

save map 29  
SILENT 68  
support 11  
symbol 24  
syntax 68, 71

system requirements 13

## - T -

toolbar 29  
total distance 31, 41, 53, 63  
trip cost 31  
trip duration 31

## - U -

uninstall 19  
utility 68

## - V -

VALUE 23, 24, 29, 68  
variable 68, 71  
variables 31, 41, 53, 63  
varName 23  
vFormattedAddress 68

## - W -

waypoint 24, 40, 52, 62  
window pane 29  
window state 29

Back Cover